



# Release Notes for Cisco AnyConnect VPN Client, Release 2.3.nnn

---

Revised: October 04, 2009, OL-18325-16

## Introduction

These release notes are for the following Cisco AnyConnect VPN Client releases:

- 2.3.2016
- 2.3.254
- 2.3.185

The AnyConnect client provides remote users with secure VPN connections to the Cisco ASA 5500 Series Adaptive Security Appliance using the Secure Socket Layer (SSL) protocol and the Datagram TLS (DTLS) protocol.

The AnyConnect client provides remote end users running Microsoft Windows Vista, Windows Mobile, Windows XP or Windows 2000, Linux, or Macintosh OS X, with the benefits of a Cisco SSL VPN client, and supports applications and functions unavailable to a clientless, browser-based SSL VPN connection. In addition, the AnyConnect client supports connecting to IPv6 resources over an IPv4 network tunnel. This release supports the SSL and DTLS protocol. This release does not include IPsec support.

The client can be loaded on the security appliance and automatically downloaded to remote users when they log in, or it can be manually installed as an application on PCs by a network administrator. After downloading, it can automatically uninstall itself after the connection terminates, or it can remain on the remote PC for future SSL VPN connections.

The client includes the ability to create user profiles that are displayed in the user interface and define the names and addresses of host computers.

These release notes describe new features, limitations and restrictions, open and resolved caveats, and related documentation. They also include procedures you should follow before loading this release. The section [Usage Notes on page 47](#) describes interoperability considerations and other issues you should be aware of when installing and using the AnyConnect client. Read these release notes carefully prior to installing this software.



---

**Americas Headquarters:**  
**Cisco Systems, Inc., 170 West Tasman Drive, San Jose, CA 95134-1706 USA**

© 2009 Cisco Systems, Inc. All rights reserved.

# Contents

This document includes the following sections:

- [New Features on page 2](#)
- [Feature Overview on page 10](#)
- [System Requirements on page 12](#)
- [Upgrading to AnyConnect Release 2.3 on page 17](#)
- [Installation Notes on page 18](#)
- [Usage Notes on page 47](#)
- [Caveats on page 59](#)
- [Notices/Licensing on page 66](#)
- [Related Documentation on page 66](#)

## New Features

The following sections describe the new features in the 2.3 releases:

- [New Features in Cisco AnyConnect VPN Client, Release 2.3.2016](#)
- [New Features in Cisco AnyConnect VPN Client, Release 2.3.254](#)
- [New Features in Cisco AnyConnect VPN Client, Release 2.3.185](#)

## New Features in Cisco AnyConnect VPN Client, Release 2.3.2016

AnyConnect VPN Client Release 2.3.2016 is primarily a quality improvement release; however, it does include the following new features.

### Ignore Proxy

This feature lets you specify a policy in the AnyConnect profile to bypass the Internet Explorer proxy configuration settings on the user's PC. It is useful when the proxy configuration prevents the user from establishing a tunnel from outside the corporate network.

To enable Ignore Proxy, insert the following line into the <ClientInitialization> section of the AnyConnect profile (*anyfilename.xml*):

```
<ProxySettings>IgnoreProxy</ProxySettings>
```



#### Note

AnyConnect currently supports only the IgnoreProxy setting; it does not support the Native and Override settings in the new ProxySettings section within the <ClientInitialization> section of the XML schema (AnyConnectProfile.xsd).

## Using PPP Exclusion to Support AnyConnect over L2TP or PPTP

AnyConnect Release 2.3.2016 introduces support for the L2TP and PPTP tunneling protocols used by ISPs in some countries, including Israel.

To send traffic destined for the ASA over a PPP connection, AnyConnect uses the point-to-point adapter generated by the external tunnel. When establishing a VPN tunnel over a PPP connection, AnyConnect must exclude traffic destined for the ASA from the tunneled traffic intended for destinations beyond the ASA. To specify whether and how to determine the exclusion route, use the PPPEXclusion configuration option.

The exclusion route appears as a non-secured route in the Route Details display of the AnyConnect GUI.

The following sections describe how to set up PPP exclusion:

- [Configuring PPP Exclusion](#)
- [Instructing Users to Override PPP Exclusion](#)

### Configuring PPP Exclusion

By default, PPP Exclusion is disabled. AnyConnect Release 2.3.2016 does not provide Profile Editor support for editing the PPP Exclusion settings. To enable PPP exclusion, insert the PPPEXclusion line shown below in bold into the <ClientInitialization> section of the AnyConnect profile (*anyfilename.xml*):

```
<AnyConnectProfile xmlns="http://schemas.xmlsoap.org/encoding/"
xmlns:xsi="http://www.w3.org/2001/XMLSchema-instance"
xsi:schemaLocation="http://schemas.xmlsoap.org/encoding/ AnyConnectProfile.xsd">
  <ClientInitialization>
    <PPPEXclusion UserControllable="true">Automatic</PPPEXclusion>
  </ClientInitialization>
  <ServerList>
    <HostEntry>
      <HostName>DomainNameofASA</HostName>
      <HostAddress>IPaddressOfASA</HostAddress>
    </HostEntry>
  </ServerList>
</AnyConnectProfile>
```

The PPPEXclusion UserControllable value true lets users read and change the PPP exclusion settings. If you want to prevent users from viewing and changing the PPP exclusion settings, change it to false.

AnyConnect supports the following PPPEXclusion values:

- **Automatic**—Enables PPP exclusion. AnyConnect automatically uses the IP address of the PPP server. Instruct users to change the value only if automatic detection fails to get the IP address.
- **Override**—Also enables PPP exclusion. If automatic detection fails to get the IP address of the PPP server, and the PPPEXclusion UserControllable value is true, instruct users to follow the instructions in the next section to use this setting.
- **Disabled**—Disables PPP exclusion by forwarding all client traffic through the VPN tunnel.

To let users view and change the IP address of the security appliance used for PPP exclusion, add the PPPEXclusionServerIP tag with its UserControllable value set to true, as shown in bold below:

```
<AnyConnectProfile xmlns="http://schemas.xmlsoap.org/encoding/"
xmlns:xsi="http://www.w3.org/2001/XMLSchema-instance"
xsi:schemaLocation="http://schemas.xmlsoap.org/encoding/ AnyConnectProfile.xsd">
  <ClientInitialization>
    <PPPEXclusion UserControllable="true">Automatic</PPPEXclusion>
    <PPPEXclusionServerIP UserControllable="true"></PPPEXclusionServerIP>
  </ClientInitialization>
</AnyConnectProfile>
```

```

</ClientInitialization>
<ServerList>
  <HostEntry>
    <HostName>DomainNameofASA</HostName>
    <HostAddress>IPaddressOfASA</HostAddress>
  </HostEntry>
</ServerList>
</AnyConnectProfile>

```

## Instructing Users to Override PPP Exclusion

AnyConnect does not currently provide UI support for PPP exclusion. If automatic detection does not work, and the PPPEXclusion UserControllable value is true, instruct the user to manually override PPP exclusion, as follows:

---

**Step 1** Use an editor such as Notepad to open the AnyConnect (*anyfilename.xml*) file.

This file is on one of the following paths on the user's computer:

- Windows: %LOCAL\_APPDATA%\Cisco\Cisco AnyConnect VPN Client\*anyfilename.xml*.  
For example,
  - Windows Vista—C:\Users\username\AppData\Local\Cisco\Cisco AnyConnect VPN Client\*anyfilename.xml*
  - Windows XP—C:\Documents and Settings\All Users\Application Data\Cisco\Cisco AnyConnect VPN Client\Profile\*anyfilename.xml*
- Mac OS X: /Users/username/.anyconnect
- Linux: /home/username/.anyconnect

**Step 2** Insert the PPPEXclusion details under <ControllablePreferences>, while specifying the Override value and the IP address of the PPP server. The address must be a well-formed IPv4 address. For example:

```

<AnyConnectPreferences>
<ControllablePreferences>
<PPPEXclusion>Override
<PPPEXclusionServerIP>192.168.22.44</PPPEXclusionServerIP></PPPEXclusion>
</ControllablePreferences>
</AnyConnectPreferences>

```

**Step 3** Save the file.

**Step 4** Exit and restart AnyConnect.

---

## New Features in Cisco AnyConnect VPN Client, Release 2.3.254

The AnyConnect client Release 2.3.1 includes one new feature and improvements to some existing features, as well as resolving numerous open caveats:

- Windows users can now establish an AnyConnect session from a single Remote Desktop Protocol (RDP) session.
- In addition, the security appliance now issues a syslog message when an older Cisco VPN client or a non-Cisco client attempts a connection to the security appliance. This syslog message is configurable and is disabled by default.

- This release includes new translation templates and a procedure for upgrading the AnyConnect client.
- You can use the Java-based utility, Cisco AnyConnect Profile Editor - Beta, as an alternative to using ASDM to create AnyConnect profiles. After using it to create a profile, you can import it to the ASA for pushing to clients. Click the AnyConnectProfileEditor.zip link adjacent to “2.3.0254” on the AnyConnect VPN Client Software Download page, download and extract the file, then see the AnyConnectProfileEditor\jar\profileEditorHelp.rtf document for instructions.

## Allow AnyConnect Session from an RDP Session for Windows Users

Some customers require the ability to log on to a client PC using Windows Remote Desktop and create a VPN connection to a secure gateway from within the Remote Desktop (RDP) session. This new feature allows a VPN session to be established from an RDP session. A split tunneling VPN configuration is required for this to function correctly. For information about split tunneling, see *Cisco ASDM User Guide* or *Cisco ASA 5500 Series Command Line Configuration Guide Using the CLI*.

The default settings for this feature retain the existing functionality: namely, a locally logged-on user can establish a VPN connection only when no other local user is logged in. The VPN connection is terminated when the user logs out, and additional local logons during a VPN connection result in the connection being torn down. Remote logons and logoffs during a VPN connection are unrestricted.



### Note

With this new feature, the AnyConnect client disconnects the VPN connection when the user who established the VPN connection logs off. If the connection is established by a remote user, and that remote user logs off, then the VPN connection is terminated.

New preference settings in the AnyConnect profile dictate how Windows logons are treated at connection establishment and during the connection. These preferences are configurable only by the network administrator. They let customers configure the client to allow VPN connection establishment from an RDP session. The end-user does not see any changes in the AnyConnect client GUI as a result of this feature. [Table 1](#) shows the new preferences.

**Table 1**      **Windows Logon Preferences**

Preference Name	Possible Values (Defaults in Bold)
WindowsLogonEnforcement	<b>SingleLocalLogon</b> SingleLogon
WindowsVPNEstablishment	<b>LocalUsersOnly</b> AllowRemoteUsers

## Windows Logon Enforcement

The WindowsLogonEnforcement preference setting determines the behavior of the AnyConnect client when a user logs on to the client PC. The possible values for this preference setting are as follows:

- **SingleLocalLogon**—(Default) Allows only one local user to be logged on during the entire VPN connection. This behavior is similar to, but not exactly the same as, the behavior in earlier releases. If more than one local user is logged on when the VPN connection is being established, the connection is not allowed. If a second local user logs on during the VPN connection, then the VPN connection is terminated.

With this setting, a local user can establish a VPN connection while one or more remote users are logged on to the client PC, but if the VPN connection is configured for all-or-nothing tunneling, then the remote logon is disconnected because of the resulting modifications of the client PC routing table for the VPN connection. If the VPN connection is configured for split-tunneling, the remote logon might or might not be disconnected, depending on the routing configuration for the VPN connection. The SingleLocalLogin setting has no effect on remote user logons from the enterprise network over the VPN connection.

- **SingleLogon**—Allows only one user to be logged on during the entire VPN connection. If more than one user is logged on, either locally or remotely, when the VPN connection is being established, the connection is not allowed. If a second user logs on, either locally or remotely, during the VPN connection, the VPN connection is terminated.

When you select the SingleLogon setting, no additional logons are allowed during the VPN connection, so a remote logon over the VPN connection is not possible.

## Windows VPN Establishment

The WindowsVPNEstablishment preference setting determines the behavior of the AnyConnect client when a user who is remotely logged on to the client PC establishes a VPN connection. The possible values are:

- **LocalUsersOnly**—(Default) Prevents a remotely logged-on user from establishing a VPN connection. This is the same functionality as in prior versions of the AnyConnect client.
- **AllowRemoteUsers**—Allows remote users to establish a VPN connection. However, if the configured VPN connection routing causes the remote user to become disconnected, the VPN connection is terminated to allow the remote user to regain access to the client PC.

Remote users must wait 90 seconds after VPN establishment if they want to disconnect their remote login session without causing the VPN connection to be terminated.

On Vista, the WindowsVPNEstablishment profile setting is not currently enforced during Start Before Logon (SBL). The AnyConnect client does not determine whether the VPN connection is being established by a remote user before logon; therefore, a remote user can establish a VPN connection via SBL even when the WindowsVPNEstablishment setting is LocalUsersOnly. Previous versions of AnyConnect also did not prevent this behavior.

## New Syslog Message for Older or Non-Cisco Clients

The AnyConnect client, Releases higher than 2.3.0185, identifies itself as an official, proprietary implementation of the Cisco SSL tunneling protocol. You can configure the security appliance to issue a system log message when an unknown implementation attempts to connect. The message also appears when a version of the AnyConnect prior to 2.3.0185 or the legacy Cisco SSL VPN client connects.

```
%hostname-6-722053: Group <g> User <u> IP <ip> Unknown client <user-agent> connection
Where:
```

- *g* is the group-policy the user logged in on.
- *u* is the username of the user.
- *ip* is the public (i.e. Internet) IP address of the user.
- *user-agent* is the user agent string from the client, indicating the version of the client the user is using.

For example:

```
%hostname-6-722053: Group <webvpn> User <sales> IP <1.2.3.4> Unknown client <Cisco
AnyConnect VPN Agent for Windows 2.3.0185> connection
```

This syslog can occur when an older, or non-supported, SSL VPN client has connected to the security appliance. Such clients include:

- Cisco SSL VPN Client (SVC).
- Cisco AnyConnect Client, Release 2.3.185 or earlier.

This message has no effect on whether the connection succeeds.

### Configuration

This syslog is disabled by default. To enable this syslog on the console, do the following:

```
hostname(config)# logging enable
hostname(config)# logging class svc console warning
```

To change the severity of this syslog to notification (5), do the following:

```
hostname(config)# logging message 722053 level notification
```

To enable just this syslog, do the following:

```
hostname(config)# logging enable
hostname(config)# logging message 722053 level emergencies
hostname(config)# logging class svc console emergencies
```

## Translation Templates and Upgrading the AnyConnect Client

Occasionally, we add new messages displayed to AnyConnect users that provide helpful information about the client connection. To enable translation of these new messages, we create new message strings and include them in the translation template packaged with the latest client image. Therefore, if you upgrade to the latest available client, you also receive the template with the new messages. However, if you have created translation tables based on the template included with the previous client, the new messages are not automatically displayed to remote users. You must merge the latest template with your translation table.

Convenient tools exist to help you merge the template and the translation table. The tools and procedure are covered in *Cisco AnyConnect VPN Client Administrator Guide*, [Merging a Newer Translation Template with your Translation Table](#), page 5-23.

## New Features in Cisco AnyConnect VPN Client, Release 2.3.185

The AnyConnect client Release 2.3 focuses on providing an improved user experience. This release includes the following new features:

- AnyConnect support for the Windows Mobile OS touch-screen devices listed in [“System Requirements” section on page 12](#) for VPN connections to Cisco Series 5500 Adaptive Security Appliances. Although AnyConnect 2.3 is designed for compatibility with Windows Mobile 6.1, 6.0 and 5.0 Professional and Classic, Cisco supports only the devices it has specifically qualified and listed in that section.



### Note

Windows Mobile requires an AnyConnect for Mobile license and must have ASA Release 8.0.3 or later running on the security appliance.

- Machine certificate access for authentication (standalone mode only). Any logged-in user on the system in standalone mode can have access to available machine certificates, as well as to user certificates, for VPN authentication.
- The AnyConnect client for Windows Mobile requires that a security appliance mobile license be installed. If the correct license is not installed, end user receives an error message.
- Dynamic Updating of the user interface when changing groups.
- Enhancements to the management of user preferences, including a new profile template and more customizable attributes.
- New profile template with all the possible preferences and comments about their use under the <ClientInitialization> tag.
  - UseStartBeforeLogon: existed in 2.2 but now it can be made user controllable (visible in the preferences dialog)
  - ShowPreConnectMessage: existed in 2.2

The rest are all new preferences under ClientInitialization:

- CertificateStoreOverride
- CertificateStore
- AutoConnectOnStart
- MinimizeOnConnect
- LocalLanAccess
- AutoReconnect and its child element AutoReconnectBehavior
- AutoUpdate
- RSASecurIDIntegration

[Table 2](#) shows the default values for these elements (if not found in the profile) and their possible values.



**Table 2**      **Default Values for Preferences Elements**

Preference Name	Preference Available by Default <sup>1</sup>	Default Value <sup>2</sup>	Possible Values <sup>3</sup>	User Control Allowed <sup>4</sup>	Default User Control <sup>5</sup>	OS <sup>6</sup>
CertificateStoreOverride	false	false	true, false	No	n/a	All
CertificateStore	false	All	All, Machine, User	No	n/a	All
ShowPreConnectMessage	false	false	true, false	No	n/a	All
AutoConnectOnStart <sup>7</sup>	true	true	true, false	Yes	True	All
MinimizeOnConnect	true	true	true, false	Yes	True	All
LocalLanAccess	true	false	true, false	Yes	True	All
AutoReconnect <sup>8</sup>	false	true	true, false	Yes	False	All
AutoReconnectBehavior	false	DisconnectOnSuspend	ReconnectAfterResume DisconnectOnSuspend	Yes	False	Windows Mac
UseStartBeforeLogon	false	True	true, false	Yes	True	Windows except mobile
AutoUpdate	false	True	true, false	Yes	False	All
RSASecurIDIntegration <sup>9</sup>	false	Automatic	Automatic, SoftwareToken, HardwareToken	Yes	False	Windows

1. Preferences available by default are visible to the user and configurable even if there is no profile in the head end.
2. The default value of a preference is used when its value is not defined in the profile.
3. The value of a preference is defined in between the preference tags; for example, <AutoUpdate>true</AutoUpdate>.
4. Preferences that don't allow user control cannot be made UserControllable; that is, even if they are defined as UserControllable="true" in the profile, this is ignored, and the default values are used.
5. The user controllable attribute is defined inside the preference tags; for example, <AutoUpdate UserControllable="true">true</AutoUpdate>. Its possible values are "true" or "false", and these determine which preferences are overridden by the *anyfilename.xml* file. This is an optional attribute, and if not defined, the default value is used. Preferences made UserControllable="true" in the profile are visible in the Preferences dialog.
6. OS that supports these preferences.
7. If you disable AutoConnectOnStart, the user must select an option in the Connect to drop-down list to establish an AnyConnect session. After the user does so, AnyConnect applies the settings of the AnyConnect client profile provided by that host.
8. See the note below to add the AutoReconnect preference.
9. The AnyConnect client is compatible with RSA SecurID software versions 1.1 and higher. At the time of this release, RSA SecurID Software Token client software does not support Windows Vista and 64-bit systems.

**Note**

AutoReconnect is a special type of preference, as it has a child preference. This is configured in the profile as:

```
<AutoReconnect UserControllable="true">true
<AutoReconnectBehavior
UserControllable="true">ReconnectAfterResume</AutoReconnectBehavior>
</AutoReconnect>
```

**Note**

Where, if `AutoReconnect` is configured as `Not UserControllable`, then `AutoReconnectBehavior` is not `UserControllable`, even if the profile says it is. If `AutoReconnect` *is* `UserControllable`, then `AutoReconnectBehavior` can be either `UserControllable` or not.

- Enhancements to Application Programming Interface (API), for customers who want to automate a VPN connection with the AnyConnect client from another application, including the following:
  - Preferences
  - Set tunnel-group method

The API package contains documentation, source files, and library files to support a C++ interface for the Cisco AnyConnect VPN Client. There are libraries and example programs that can be used for building on Windows, Linux and MAC (10.4 or higher) platforms. The Makefiles (or project files) for the Windows platform are also included. For other platforms, there is a platform specific script showing how to compile the example code. Network administrators can link their application (GUI, CLI, or embedded application) with these files and libraries.

## Feature Overview

In addition to the new features listed above, the Cisco AnyConnect VPN Client provides remote users with secure VPN connections to the Cisco 5500 Series Adaptive Security Appliance.

Additional features of the AnyConnect client include:

- Support for Start Before Logon for Windows Vista systems, in addition to other Windows operating systems.
- Extended customization and localization features—This version of the AnyConnect client includes enhanced customization features and language translation features. In previous versions, you could customize client installations only on an individual PC basis. With this version, the security appliance can customize the client as it downloads and installs the client on the remote PC. You can also translate the client installer. These extended features include the following items:
  - Localized installs using localized MSI transforms (Windows only).
  - Custom MSI transforms (Windows only).
  - User-defined resource files.
  - Third-party GUI/CLI support.
  - Localization for Mac OS X 10.4 and 10.5.
- System tray in Windows systems now shows an icon when the AnyConnect client is reconnecting after losing connectivity.
- Enhanced Network Mobility—A user can lose connectivity for an extended period of time and still be able to have the client automatically resume the connection, as long as the security appliance has not logged the session off. In addition, a VPN session can now be retained during a hibernate/standby condition. This does not require any configuration changes; it is automatically enabled. The VPN tunnel might be dropped if the hibernation/sleep time exceeds the idle connection timeout or session timeout configured on the security appliance. You can also restrict this feature by setting the idle session timeout to a low value.

In earlier versions, the tunnel would be automatically torn down when a system entered suspend or hibernate. For Windows Vista, please see the usage note on this topic “[Network Subsystem on Windows Vista Might Become Unresponsive During Sleep/Resume Cycles or Other High-load Conditions \(KB-952876\)](#)” section on page 51.

- Application Programming Interface (API), for customers who want to automate a VPN connection with the AnyConnect client from another application.
- Datagram Transport Layer Security (DTLS) with SSL connections—Avoids latency and bandwidth problems associated with some SSL-only connections and improves the performance of real-time applications that are sensitive to packet delays. DTLS is a standards-based SSL protocol that provides a low-latency data path using UDP. For detailed information about DTLS, see RFC 4347 (<http://www.ietf.org/rfc/rfc4347.txt>).
- Standalone Mode—Allows a Cisco AnyConnect VPN client to be established as a PC application without the need to use a web browser to establish a connection.
- Command Line Interface (CLI)—Provides direct access to client commands at the command prompt.
- Microsoft Installer (MSI)—Gives Windows users a pre-install package option that provides installation, maintenance, and removal of AnyConnect client software on Windows systems.
- IPv6 VPN access—Allows access to IPv6 resources over a public IPv4 connection (Windows XP SP2, Windows Vista, Mac OSX, and Linux only). See the [Usage Notes](#) section for information about setting up IPv6 access.
- Start Before Logon (SBL)—Allows for login scripts, password caching, drive mapping, and more, for Windows.
- Certificate-only authentication—Allows users to connect with digital certificate and not provide a user ID and password.
- Simultaneous AnyConnect client and clientless, browser-based connections.
- Compression—Increases the communications performance between the security appliance and the client by reducing the size of the packets being transferred. Compression works only for TLS.
- Fallback from DTLS to TLS—Provides a way of falling back from DTLS to TLS if DTLS is no longer working.
- Language Translation (localization)—Provides a way of implementing translation for user messages that appear on the client user interface.
- Dynamic Access Policies feature of the security appliance—Lets you configure authorization that addresses the variables of multiple group membership and endpoint security for VPN connections.
- Cisco Secure Desktop (CSD) support—Validates the security of client computers requesting access to your SSL VPN, helps ensure they remain secure while they are connected, and attempts to remove traces of the session after they disconnect. AnyConnect supports the Host Scan component of Cisco Secure Desktop on Windows XP and Windows 2000. Cisco Secure Desktop does not support the AnyConnect client within the Secure Desktop (Vault) on Windows Vista systems.
- Rekey—Provides the ability to renegotiate the key used to encrypt data packets throughout the life of the VPN connection.

# System Requirements

If you are using Internet Explorer, use version 5.0, Service Pack 2 or later.

AnyConnect does not support virtualization software, such as VMWare for any platform or Parallels Desktop for Mac OS. Although initial testing suggests that AnyConnect 2.4 running over VMware or Microsoft Virtual PC on Windows 7 will generally work, it has never been fully tested and is not guaranteed to be 100% reliable.

AnyConnect does not support sessions with a security appliance running on the same subnet.

## Microsoft Windows

If you are using Internet Explorer, use version 5.0, Service Pack 2 or later. For WebLaunch, use Internet Explorer 6.0+ or Firefox 2.0+, and enable ActiveX or install Sun JRE 1.4+.

### Windows Versions

- Windows Vista—32- and 64-bit Microsoft Windows Vista SP2 or Vista Service Pack 1 with KB952876.
- Windows XP SP2 and SP3.
- Windows 2000 SP4.

### Windows Requirements

- Pentium class processor or greater.
- x64 or x86 processors on Windows XP and Windows Vista.
- 5 MB hard disk space.
- RAM:
  - 128 MB for Windows 2000.
  - 256 MB for Windows XP.
  - 512 MB for Windows Vista.
- Microsoft Installer, version 3.1.

## Linux

The following sections show the Linux distributions and requirements.

### Linux Distributions

AnyConnect supports Linux Kernel releases 2.4 and 2.6 on 32-bit architectures, and 64-bit architectures that support biarch (that is, that run 32-bit code).

The following Linux distributions follow the requirements and work with the AnyConnect Client:

- Ubuntu 7 and 8 (32-bit only).
- Red Hat Enterprise Linux 3 or 4. (As of publication, we have not tested AnyConnect with Red Hat Linux 5.
- Fedora Core 4 through 9. To use Fedora 9 with the AnyConnect client, you must first install Sun Microsystems JRE, preferably JRE 6, Update 5 or higher.

- Slackware 11 or 12.1.
- openSuSE 10 or SuSE 10.1.

### Linux Requirements

- x86 instruction set.
- 32-bit or biarch 64-bit processor—standalone mode only; web-based install/connect is not supported.
- 32 MB RAM.
- 20 MB hard disk space.
- Superuser privileges.
- libstdc++ users must have libstdc++ version 3.3.2 (libstdc++.so.5) or higher, but below version 4.
- Firefox 2.0 or later with libnss3.so installed in /usr/local/lib, /usr/local/firefox/lib, or /usr/lib. Firefox must be installed in /usr/lib or /usr/local, or there must be a symbolic link in /usr/lib or /usr/local called firefox that points to the Firefox installation directory.
- libcurl 7.10 or later.
- openssl 0.9.7a or later.
- java 1.5 or later. The default Java package on Fedora is an open-source GNU version, called Iced Tea on Fedora 8. The only version that works for web installation is Sun Java. You must install Sun Java and configure your browser to use that instead of the default package.
- zlib or later.
- gtk 2.0.0,  
gdk 2.0.0,  
libpango 1.0.
- iptables 1.2.7a or later.
- tun module supplied with kernel 2.4.21 or 2.6.








## Mac OS

AnyConnect supports Mac OS X Versions 10.4 and 10.5. It requires 50 MB hard disk space.

## Windows Mobile

Cisco designed AnyConnect 2.3 for compatibility with Windows Mobile 6.1, 6.0 and 5.0 Professional and Classic for touch-screens only, but has specifically qualified only the devices listed in [Table 3](#) to ensure interoperability. While other devices might work, Cisco does not guarantee compatibility with other devices. [Table 3](#) lists the supported devices with their corresponding service providers and supported operating system versions.

**Table 3** *Supported Windows Mobile Devices (Touch-screens Only)*

Device	OS	Wi-Fi
ATT Tilt 3.57.502.2 WWE <b>Note:</b> TouchFLO must be disabled.	Windows Mobile 6.1 Professional	
Axim X51v with ROM: A03 (23092007)	Windows Mobile 6.0 Classic	
iPAQ 2790	Windows Mobile 5.0 PocketPC	
Sprint Touch with ROM: 3.03.651.4 <b>Note:</b> TouchFLO must be disabled.	Windows Mobile 6.1 Professional	—
T-Mobile Wing 4.26.531.1 WWE	Windows Mobile 6.0 Professional	
Palm Treo 700wx: • Sprint TREO 700WX-1.15-SPNT	Windows Mobile 5.0+AKU2 PDA Phone	—
Palm Treo 750: • AT&T TREO750-2.27-RWE • AT&T TREO 750-2.25-ATT • T-Mobile TREO750-2.27-RWE	Windows Mobile 6.0 Professional	—
Palm Treo 800: • Sprint Treo 800w-1.03-SPNT	Windows Mobile 6.1 Professional	
Palm Treo Pro: • AT&T T850UNA-1.01-NAE • Sprint T850EWW-1.03-SPT • T-Mobile T850UNA-1.01-NAE	Windows Mobile 6.1 Professional	
Verizon XV6800 with ROM: 1.00.00.H: • Verizon 2.09.605.8 • Verizon 3.57.605.1	Windows Mobile 6.0 Professional and Windows Mobile 6.0 Professional	

## Security Appliances and Software Supported

The Cisco AnyConnect VPN Client supports all Cisco Adaptive Security Appliance models. It does not support PIX devices. See the Adaptive Security Appliance VPN Compatibility Reference: <http://www.cisco.com/en/US/docs/security/asa/compatibility/asa-vpn-compatibility.html> for a complete list of compatibility requirements.

Table 4 shows the minimum Cisco ASA 5500 Adaptive Security Appliance software images that support the AnyConnect client.

**Table 4**      **Software Images that Support the AnyConnect Client, Release 2.3**

Image Type	Version
ASA Boot image	8.0(3).1 or later
Adaptive Security Device Manager (ASDM)	6.1(3).1 or later
Cisco AnyConnect VPN Client	Windows, Linux, and Mac OS X: 2.3
Cisco Secure Desktop	3.2(2) <sup>1</sup>

1. Cisco Secure Desktop, Release 3.2(1) is compatible, but it provides more limited functions.

## Interoperability Considerations

This section describes how the AnyConnect VPN Client interoperates with other software. The AnyConnect client can be loaded on the security appliance and automatically deployed to remote users when they log in to the security appliance, or it can be installed as an application on PCs by a network administrator using standard software deployment mechanisms. You can use a text editor to create user profiles as XML files. These profiles drive the display in the user interface and define the names and addresses of host computers.

### AnyConnect Client and Cisco Secure Desktop

See the Adaptive Security Appliance VPN Compatibility Reference: <http://www.cisco.com/en/US/docs/security/asa/compatibility/asa-vpn-compatibility.html> for a complete list of compatibility requirements.

There is no support of the AnyConnect client within Secure Desktop (Vault) on the Windows Vista platform in Release 3.3 of Cisco Secure Desktop. Do not configure the AnyConnect client and Secure Desktop (Vault) if your users use the Windows Vista platform. This limitation applies only to AnyConnect client users who are using the Windows Vista platform. Users who connect using a clientless connection *can* use the Secure Desktop (Vault).

If you must configure the AnyConnect client and Cisco Secure Desktop secure desktop, but some of your users might be on the Windows Vista platform, consider using Cisco Secure Desktop, Release 3.2.1 to accomplish this. In this case, Secure Desktop (Vault) is started only on non-Vista platforms (otherwise, Cache Cleaner is invoked in its place for the clientless environment).

If you want to enforce Cisco Secure Desktop secure desktop for certain users, and you expect that AnyConnect will also be used for those users who may use Windows Vista or Windows XP, you can, through prelogin policy, configure a policy that starts Cache Cleaner or Hostscan (in place of Secure Desktop) for users on Windows Vista platforms. For example, the policy can key off the registry value: HKEY\_LOCAL\_MACHINE\Software\Microsoft\Windows NT\CurrentVersion\CurrentVersion

**Note**

Cisco Secure Desktop does not support AnyConnect Windows Mobile, and AnyConnect Windows Mobile does not connect to a host that has Cisco Secure Desktop enabled. If the device is a Windows Mobile device or the iPhone, it bypasses Cisco Secure Desktop, even if Cisco Secure Desktop is enabled.

## AnyConnect and Citrix

There exists a conflict between AnyConnect and Citrix Advanced Gateway client 2.2.1.

When disconnecting AnyConnect, users can receive this Microsoft Windows error: “VPN Agent Service has encountered a problem and needs to close. We are sorry for the inconvenience.” After clicking close on the Microsoft Windows error, users receive this next message from AnyConnect: “Unable to Proceed. Cannot contact the VPN service.” Finally, at the bottom of the AnyConnect client window, users receive the message: “The VPN Service has failed. Please restart the application” This indicates the AnyConnect Agent service has crashed.

The Citrix client installs a Layered Service Provider DLL (CtxLsp.dll) that it loads into every process using Windows Sockets (WinSock). As such, this DLL is loaded into the AnyConnect Agent Service. The crash occurs as a result of this DLL being part of the Agent process. The crashes always occur during freeing of memory because of memory heap corruptions caused by this DLL. These same operations work correctly when the DLL is not part of the process. The crashes have been seen to occur in the downloader application as well, and even in the FileZilla FTP Server.

While the crashes occur very frequently, they do not always occur. Also, the crashes occur in different places in the process, but they are always the result of a memory heap corruption. The bug is in the Citrix DLL. Others have reported this issue to Citrix:

<http://support.citrix.com/forums/thread.jspa?forumID=60&threadID=80923&tstart=15>

The current workaround for this problem is to disable the Citrix client.

## AnyConnect and IOS

Several features of the Cisco AnyConnect VPN Client are supported in conjunction with various IOS routers with SSL VPN support. Please see the system requirements listed in the [Cisco IOS SSL VPN Data Sheet](#) for specific details about supported features for IOS devices and the IOS [SSL VPN](#) feature guide for configuration details. If you are a remote user, see the IOS [SSL VPN Remote User Guide](#) for configuration information.

## AnyConnect and PIX

PIX does not support SSL VPN connections, either clientless or AnyConnect.



# Upgrading to AnyConnect Release 2.3

This section contains information about upgrading from the Cisco SSL VPN Client to Cisco AnyConnect VPN Client, Release 2.3.

Before you begin, be aware of the considerations listed in the [Usage Notes on page 47](#), section of these Release Notes before you upgrade. These are known product behaviors, and knowing about them at the beginning of the process should expedite the upgrade. Where appropriate, the number of the caveat documenting the issue appears at the end of the item. See the [“Caveats” section on page 59](#) for a list of open and resolved caveats.

## End User Interface

[Figure 1](#) shows the Cisco AnyConnect VPN Client user interface. The Connection tab provides a drop-down list of profiles for connecting to remote systems.

**Figure 1** *Cisco AnyConnect VPN Client User Interface, Connection Tab*



Figure 2 shows the Statistics tab, including current connection information.

**Figure 2** *Cisco AnyConnect VPN Client User Interface, Statistics Tab*



## AnyConnect Client Disconnect Behavior

If you click Disconnect, the AnyConnect client, starting with Release 2.3, terminates the connection, as shown in the status bar at the bottom of the dialog box, and the AnyConnect GUI displays a login dialog box with a “Connect to” combo box and a Select button. To reconnect, the remote user must select a new host server to connect to or click Select. At that point, the appropriate authentication prompts are displayed.

## Installation Notes

This section contains procedures for installing the AnyConnect client software on the ASA5500 using the Adaptive Security Device Manager (ASDM) or the CLI command interface.

### WebLaunch Mode

Without a previously-installed client, remote users enter the IP address or DNS name in their browser of an interface configured to accept clientless SSL VPN connections. Local system admin privileges are required if the client is not already installed. Unless the security appliance is configured to redirect http:// requests to https://, users must enter the URL in the form https://<address>. Weblaunch mode can also be used even when the client is already installed.



#### Note

A user with a clientless SSL VPN connection can switch to an AnyConnect client vpn connection by clicking the Network Access drawer on the portal and following the instructions on that page.

After the user enters the URL, the browser connects to that interface and displays the login screen. If the user satisfies the login and authentication, and the security appliance identifies the user as requiring the client, it loads the client that matches the operating system of the remote computer. After loading, the client installs and configures itself, establishes a secure SSL connection and either remains or uninstalls itself (depending on the security appliance configuration) when the connection terminates.

### Standalone Mode

In the case of a previously-installed client, when the user authenticates, the security appliance examines the revision of the client, and upgrades the client as necessary.

When the client negotiates an SSL VPN connection with the security appliance, it connects using Transport Layer Security (TLS). The client can also negotiate a simultaneous Datagram Transport Layer Security (DTLS) connection. DTLS avoids latency and bandwidth problems associated with some SSL connections and improves the performance of real-time applications that are sensitive to packet delays.

The AnyConnect client can be downloaded from the security appliance, or it can be installed manually on the remote PC by the system administrator. For more information about configuring the AnyConnect client, see the *Cisco 5500 Series Adaptive Security Appliance CLI Configuration Guide*. For more detailed information about configuring the AnyConnect client and other SSL VPN connections on the security appliance, see “Configuring SSL VPN Connections” in *Cisco Security Appliance Command Line Configuration Guide*. For detailed descriptions of the commands referred to in this administrator’s guide, see the *Cisco ASA 5500 Command Reference Guide* for version 8.0 or later.

The security appliance loads the client based on the group policy or username attributes of the user establishing the connection. You can configure the security appliance to automatically load the client, or you can configure it to prompt the remote user about whether to download the client. In the latter case, if the user does not respond, you can configure the security appliance either to load the client after a timeout period or to present the login page.

The installation and configuration consists of two parts: what you have to do on the security appliance, and what you have to do on the remote PC. The AnyConnect client software is built into the ASA Release 8.0(1) and later. You can decide whether to make the AnyConnect client software permanently resident on the remote PC, or whether to have it resident only for the duration of the connection. We recommend keeping the client resident on the system, as doing so can speed up subsequent connection attempts.



#### Note

When using Start Before Logon, the VPN Gina (VPN Graphical Identification and Authentication) can not be installed dynamically if the AnyConnect client is installed manually. The VPN Gina can be installed either before or after the AnyConnect client, but they must either be both installed manually or both installed dynamically.

This section describes installation-specific issues and procedures for AnyConnect client Release 2.3, and contains the following sections:

- [Where to Find the AnyConnect Client Files for Installation on page 20](#)
- [Suggested Practice for the Position of the Windows Mobile Package on the Security Appliance on page 20](#)
- [Before You Install the AnyConnect Client on page 21](#)
- [Installing the AnyConnect Client on a System Running Windows on page 24](#)
- [Installing the AnyConnect Client on Linux on page 26](#)
- [Installing the AnyConnect Client on Mac OS on page 27](#)
- [Installing the AnyConnect Client on a Windows Mobile Device on page 28](#)

- [Loading the AnyConnect Client and Configuring the Security Appliance with ASDM on page 30](#)
- [Loading the AnyConnect Client and Configuring the Security Appliance with CLI on page 38](#)

## Where to Find the AnyConnect Client Files for Installation

All of the AnyConnect clients are located in the same place:

<http://www.cisco.com/cgi-bin/tablebuild.pl/anyconnect>

The AnyConnect client packages are as follows:

- `anyconnect-win-2.3.0254-k9.pkg`—Contains AnyConnect, vpngina, and DART.
- `anyconnect-no-dart-win-2.3.0254-k9.pkg`—Contains AnyConnect, vpngina, but *not* DART.

In addition, you can download and load the following AnyConnect files from the same location:

- **AnyConnect translation file**—`anyconnect.po_2.3.0254.zip`
- **AnyConnect API**—`anyconnect_API_2.3.0254.zip`
- **DART** (Diagnostic AnyConnect Reporting Tool)—The downloads containing DART are as follows:
  - `anyconnect-win-2.3.00254-k9.pkg`—Contains AnyConnect, vpngina, and DART.
  - `anyconnect-dart-win.msi`—Contains *only* the DART installation package, not the AnyConnect or vpngina software.



### Note

The download `anyconnect-no-dart-win-2.3.0254-k9.pkg` contains AnyConnect and vpngina software, but *not* DART.

Within the DART zip file is an msi that can be extracted and installed like other MS msi. DART creates a program group under Start -> All Programs -> Cisco -> Cisco DART. By default, the output file is available via a Desktop icon named “DARTBundle.zip”.

## Suggested Practice for the Position of the Windows Mobile Package on the Security Appliance

You must store the AnyConnect image on the security appliance to support AnyConnect for remote users even if the AnyConnect image is already deployed. You can improve the connection times by storing the Windows Mobile package in the first package slot. For example:

### Recommended:

- `svc image disk0:/AC-WINCE-23061.pkg 1`
- `svc image disk0:/AC-MACPPC-220139.pkg 2`
- `svc image disk0:/AC-LINUX-220139.pkg 3`
- `svc image disk0:/AC-WIN-220144.pkg 4`
- `svc image disk0:/AC-MAC386-220139.pkg 5`

### Not recommended:

- `svc image disk0:/AC-MACPPC-220139.pkg 1`

- `svc image disk0:/AC-LINUX-220139.pkg 2`
- `svc image disk0:/AC-WIN-220144.pkg 3`
- `svc image disk0:/AC-MAC386-220139.pkg 4`
- `svc image disk0:/AC-WINCE-23061.pkg 5`

## Before You Install the AnyConnect Client

The following sections contain recommendations to ensure successful AnyConnect client installation, as well as tips about certificates, Cisco Security Agent (CSA), adding trusted sites, and responding to browser alerts:

- [Ensuring Automatic Installation of AnyConnect Clients on page 21](#)
- [AnyConnect Client and New Windows 2000 Installations on page 22](#)
- [Adding a Security Appliance to the List of Trusted Sites \(IE\) on page 22](#)
- [Adding a Security Certificate in Response to Browser Alert Windows on page 23](#)

## Ensuring Automatic Installation of AnyConnect Clients

The following recommendations and caveats apply to the automatic installation of AnyConnect client software on client PCs:

- To minimize user prompts during AnyConnect client setup, make sure certificate data on client PCs and on the security appliance match:
  - If you are using a Certificate Authority (CA) for certificates on the security appliance, choose one that is already configured as a trusted CA on client machines.
  - If you are using a self-signed certificate on the security appliance, be sure to install it as a trusted root certificate on clients.

The procedure varies by browser. See the procedures that follow this section.

- Make sure the Common Name (CN) in security appliance certificates matches the name clients use to connect to it. By default, the security appliance certificate CN field is its IP address. If clients use a DNS name, change the CN field on the security appliance certificate to that name.

If the certificate has a SAN (Subject Alternate Name) then the browser will ignore the CN value in the Subject field and look for a DNS Name entry in the SAN field.

If users connect to the ASA using its hostname, the SAN should contain the hostname and domain name of the ASA. For example, the SAN field would contain

`DNS Name=hostname.domain.com.`

If users connect to the ASA using its IP address, the SAN should contain the IP address of the ASA. For example, the SAN field would contain `DNS Name=209.165.200.254.`

- The Cisco Security Agent (CSA) might display warnings during the AnyConnect client installation.

Current shipping versions of CSA do not have a built-in rule that is compatible with the AnyConnect client. You can create the following rule using CSA version 5.0 or later by following these steps:

---

**Step 1** In Rule Module: “Cisco Secure Tunneling Client Module”, add a FACL:

Priority Allow, no Log, Description: “Cisco Secure Tunneling Browsers, read/write vpnweb.ocx”

Applications in the following class: "Cisco Secure Tunneling Client - Controlled Web Browsers"

Attempt: Read file, Write File

On any of these files: @SYSTEM\vpnweb.ocx

- Step 2** Application Class: "Cisco Secure Tunneling Client - Installation Applications" add the following process names:

\*\*\vpndownloader.exe

@program\_files\\*\*\Cisco\Cisco AnyConnect VPN Client\vpndownloader.exe

This rule will be built into a future version of CSA.

We recommend that Microsoft Internet Explorer (MSIE) users add the security appliance to the list of trusted sites, or install Java. The latter enables the ActiveX control to install with minimal interaction from the user. This is particularly important for users of Windows XP SP2 with enhanced security. Windows Vista users *must* add the security appliance to the list of trusted sites in order to use the dynamic deployment feature. For information about adding a security appliance to the list of trusted sites, see the *Cisco AnyConnect VPN Client Administrator Guide*. For information about how to use Microsoft Active Directory to add the security appliance to the list of trusted sites for Internet Explorer, see Appendix B of *Cisco AnyConnect VPN Client Administrator Guide*.

## AnyConnect Client and New Windows 2000 Installations

In rare circumstances, if you install the AnyConnect client on a computer that has a new or clean Windows 2000 installation, the AnyConnect client might fail to connect, and your computer might display the following message:

The required system DLL (*filename*) is not present on the system.

This could occur if the computer does not have the file MSVCP60.dll or MSVCRT.dll located in the winnt\system32 directory. For more information about this problem, see the Microsoft Knowledge Base, article 259403, at <http://support.microsoft.com/kb/259403>.

## Adding a Security Appliance to the List of Trusted Sites (IE)

To add a security appliance to the list of trusted sites, use Microsoft Internet Explorer and do the following steps.



### Note

This is required on Windows Vista to use WebLaunch.

- Step 1** Go to Tools | Internet Options | Trusted Sites.  
The Internet Options window opens.
- Step 2** Click the Security tab.
- Step 3** Click the Trusted Sites icon.
- Step 4** Click Sites.

- The Trusted Sites window opens.
- Step 5** Type the host name or IP address of the security appliance. Use a wildcard such as `https://*.yourcompany.com` to allow all ASA 5500s within the `yourcompany.com` domain to be used to support multiple sites.
- Step 6** Click Add.
- Step 7** Click OK.
- The Trusted Sites window closes.
- Step 8** Click OK in the Internet Options window.
- 

## Adding a Security Certificate in Response to Browser Alert Windows

This section explains how to install a self-signed certificate as a trusted root certificate on a client in response to the browser alert windows.

### In Response to a Microsoft Internet Explorer “Security Alert” Window

The following procedure explains how to install a self-signed certificate as a trusted root certificate on a client in response to a Microsoft Internet Explorer Security Alert window. This window opens when you establish a Microsoft Internet Explorer connection to a security appliance that is not recognized as a trusted site. The upper half of the Security Alert window shows the following text:

Information you exchange with this site cannot be viewed or changed by others.  
However, there is a problem with the site's security certificate. The security certificate was issued by a company you have not chosen to trust. View the certificate to determine whether you want to trust the certifying authority.

Install the certificate as a trusted root certificate as follows:

- 
- Step 1** Click View Certificate in the Security Alert window.
- The Certificate window opens.
- Step 2** Click Install Certificate.
- The Certificate Import Wizard Welcome opens.
- Step 3** Click Next.
- The Certificate Import Wizard – Certificate Store window opens.
- Step 4** Select “Automatically select the certificate store based on the type of certificate.”
- Step 5** Click Next.
- The Certificate Import Wizard – Completing window opens.
- Step 6** Click Finish.
- Step 7** Another Security Warning window prompts “Do you want to install this certificate?” Click Yes.
- The Certificate Import Wizard window indicates the import is successful.
- Step 8** Click OK to close this window.
- Step 9** Click OK to close the Certificate window.
- Step 10** Click Yes to close the Security Alert window.

The security appliance window opens, signifying the certificate is trusted.

---

#### **In Response to a Netscape, Mozilla, or Firefox “Certified by an Unknown Authority” Window**

The following procedure explains how to install a self-signed certificate as a trusted root certificate on a client in response to a “Web Site Certified by an Unknown Authority” window. This window opens when you establish a Netscape, Mozilla, or Firefox connection to a security appliance that is not recognized as a trusted site. This window shows the following text:

Unable to verify the identity of <Hostname\_or\_IP\_address> as a trusted site.

Install the certificate as a trusted root certificate as follows:

---

- Step 1** Click the Examine Certificate button in the “Web Site Certified by an Unknown Authority” window. The Certificate Viewer window opens.
- Step 2** Click the “Accept this certificate permanently” option.
- Step 3** Click OK.

The security appliance window opens, signifying the certificate is trusted.

---

## **Installing the AnyConnect Client on a System Running Windows**

To install the AnyConnect client on a PC running Windows, follow these steps. We suggest you accept the defaults unless your system administrator has instructed otherwise.



#### **Note**

Vista users must add the security appliance to the trusted zone for automatic installation by the security appliance to work.

---

- Step 1** Exit all Windows programs, and disable any antivirus software.
  - Step 2** Download the AnyConnect client package file from the Cisco site.
  - Step 3** Double-click the package file. The welcome screen for the Cisco AnyConnect VPN Client Setup Wizard displays.
  - Step 4** Click **Next**. The End-User License Agreement displays. Accept the license agreement and click OK. The Select Installation Folder screen displays.
  - Step 5** Accept the default folder or enter a new folder and click **Next**. The Ready to Install screen displays.
  - Step 6** Click **Install**. The client installs and displays the status bar during installation. After installing, the Completing the Cisco AnyConnect VPN Client Setup Wizard screen displays.
  - Step 7** Click **Next**. The wizard disappears and the installation is complete.
-



## Installing Start Before Logon Components (Windows Only)

The Start Before Logon components must be installed *after* the core client has been installed. Additionally, the AnyConnect 2.3 Start Before Logon components require that version 2.3, or later, of the core AnyConnect client software be installed. If you are pre-deploying the AnyConnect client and the Start Before Logon components using the MSI files (for example, you are at a big company that has its own software deployment—Altiris or Active Directory or SMS.) then you must get the order right. The order of the installation is handled automatically when the administrator loads AnyConnect if it is web deployed and/or web updated.

Both the AnyConnect client and the Start Before Login components must be installed same way, either both manually or both via weblaunch. Therefore:

- If you pre-deploy AnyConnect, you must also pre-deploy the Start Before Logon components.
- If you web-update AnyConnect, you must web-update the Start Before Logon components.
- If you web-deploy AnyConnect, you must web-deploy the Start Before Logon components.
- You cannot pre-deploy AnyConnect, and then web-deploy the Start Before Logon components.

If you manually uninstall either the pre-Vista Start Before Logon component GINA or the Windows Vista Start Before Logon component PLAP, you must manually reinstall it.

You can, for example, pre-deploy both of them... put a new version of both on the head end and web-update them both. The two are joined together in whatever action you perform.

For example, a customer sends out laptops with the software pre-installed. Six months later, Cisco ships a new version of the software and the network administrators want all their users to get the latest version. To do this, the network administrators can put the new software on the security appliance, and all users get the web update.

They could *not* pre-image with just core AnyConnect software and then decide to update via the security appliance both the client and the Start Before Logon software components, since they never pre-installed the Start Before Logon software to begin with.

## Differences Between Windows-Vista and Pre-Vista Start Before Logon

The procedures for enabling SBL differ slightly on Windows Vista systems. Pre-Vista systems use a component called VPNGINA (which stands for virtual private network graphical identification and authentication) to implement SBL. Vista systems use a component called PLAP to implement SBL.

In the AnyConnect client, the Windows Vista Start Before Logon feature is known as the Pre-Login Access Provider (PLAP), which is a connectable credential provider. This feature lets network administrators perform specific tasks, such as collecting credentials or connecting to network resources, prior to login. PLAP provides start Before Logon functions on Windows Vista. PLAP supports 32-bit and 64-bit versions of the operating system with vpnplap.dll and vpnplap64.dll, respectively. The PLAP function supports Windows Vista x86 and x64 versions.



### Note

In this section, VPNGINA refers to the Start Before Logon feature for pre-Vista platforms, and PLAP refers to the Start Before Logon feature for Windows Vista systems.

In pre-Vista systems, Start Before Logon uses a component known as the VPN Graphical Identification and Authentication Dynamic Link Library (vpngina.dll) to provide Start Before Logon capabilities. The Windows PLAP component, which is part of Windows Vista, replaces the Windows GINA component.

A GINA is activated when a user presses the Ctrl+Alt+Del key combination. With PLAP, the Ctrl+Alt+Del key combination opens a window where the user can choose either to log in to the system or to activate any Network Connections (PLAP components) using the Network Connect button in the lower-right corner of the window.

For a complete description of enabling, configuring, and using the Start Before Logon feature (VPNGINA or PLAP) on a Windows platform, see *Cisco AnyConnect VPN Client Administrator Guide*, Chapter 4.

## Fulfilling Requirements for Biarch Linux

If you are running 64-bit Linux, prepare it to run 32-bit AnyConnect binary files, as follows:

- 
- Step 1** Install the following packages:
- ia32-libs
  - lib32nss-mdns.
- Step 2** Install 32-bit Firefox into the /usr/local/firefox directory.
- Step 3** Copy or link the following files from /usr/local/firefox to either /usr/lib32 or /opt/cisco/vpn/lib:
- libnssutil3.so
  - libplc4.so
  - libplds4.so
  - libnspr4.so
  - libsqlite3.so
  - libnssdbm3.so
  - libfreebl3.so
- 

## Installing the AnyConnect Client on Linux

To install the AnyConnect client on Linux, follow these steps:

- 
- Step 1** For Linux, the client files are contained in a tar/gz file. Unpack the archive with a **tar** command. For example:

```
tar xvzf AnyConnect-Linux-Release-2.3.xxxx.tar.gz
```

The files necessary for installation are placed in the folder *ciscovpn*.

- Step 2** Change to the *ciscovpn* folder. As a root user, run the script named *vpn\_install.sh*. For example:

```
[root@linuxhost]# cd ciscovpn
[root@linuxhost]# ./vpn_install.sh
```

The client installs in the directory */opt/cisco/vpn*. This script also installs the daemon *vpnagentd* and sets it up as a service that is automatically started when the system boots.

---

After installing the client, you can start the client manually with the Linux command `/opt/cisco/vpn/bin/vpnui` or with the client CLI command `/opt/cisco/vpn/bin/vpn`.

## Installing the AnyConnect Client on Mac OS

You can use the WebLaunch procedure to start AnyConnect from the clientless portal page, or you can install AnyConnect using the following standalone procedure. The section that follows describes what to do if the Java installer fails during an attempt to use WebLaunch to install AnyConnect.

### Using the Standalone Install Procedure on Mac OS

The AnyConnect client image for Mac OS is a DMG disk image installation package. To install the AnyConnect client on a system running Mac OS, follow these steps:

- 
- Step 1** Transfer the installation package file to the desktop and double-click the file. A window opens showing an icon representing the installation package file.
  - Step 2** Double-click the icon to initiate the installation. A dialog window appears asking you to select the device on which to install the client.
  - Step 3** Select a device and click **Next**. A dialog to accept the licensing agreement (EULA) appears.
  - Step 4** Accept the license agreement and click **Next**.  
The installation is complete.
- 

### Using the Manual Install Option on Mac OS if the Java Installer Fails during WebLaunch

If you use WebLaunch to start AnyConnect on a Mac and the Java installer fails, a dialog box presents a Manual Install link. Proceed as follows:

- 
- Step 1** Click **Manual Install**.  
A dialog box presents the option to save the `vpnsetup.sh` file.
  - Step 2** Save the `vpnsetup.sh` file on the Mac.
  - Step 3** Open a Terminal window and use the `CD` command to navigate to the directory containing the file saved.
  - Step 4** Enter the following command:  

```
sudo /bin/sh vpnsetup.sh
```

  
The `vpnsetup` script starts the AnyConnect installation.
  - Step 5** Following the installation, choose Applications > Cisco > Cisco AnyConnect VPN Client to initiate an AnyConnect VPN session.
-

## Installing the AnyConnect Client on a Windows Mobile Device

The security appliance does not support WebLaunch of AnyConnect on a mobile device; therefore, mobile users must download and install AnyConnect Client for Windows Mobile. Just as you can do so with corporate computers, you can pre-deploy AnyConnect on Windows Mobile devices issued to employees.

Perform the following steps to download and install AnyConnect Client for Windows Mobile.

- 
- Step 1** Download any of the following files from the Cisco AnyConnect VPN Client Download Software site to get the Windows Mobile Client:
- File containing all client installation packages:  
anyconnect-all-packages—*AnyConnectRelease\_Number-k9.zip*
  - CAB package signed by Cisco for Windows Mobile devices:  
anyconnect-wince-ARMv4I-*AnyConnectRelease\_Number-k9.cab*
  - ActiveSync MSI package for Windows Mobile platforms:  
anyconnect-wince-ARMv4I-activesync-*AnyConnectRelease\_Number-k9.msi*
- Step 2** Unzip the anyconnect-all-packages—*AnyConnectRelease\_Number-k9.zip* file if you chose to download that file.
- Step 3** Transfer the file to a corporate server if you want to provide users with a link to the client.
- Step 4** Make sure the Windows Mobile device meets the system requirements in the latest [AnyConnect Release Notes](#).
- Step 5** Use your preferred method to transfer the .cab or .msi file from your intranet server or local computer to the mobile device. Some examples include:
- Microsoft ActiveSync over radio
  - HTTP, FTP, SSH, or shared files over the LAN or radio
  - Bluetooth
  - (USB) Cable
  - Media card transfer
- Step 6** Use the mobile device to open the file you transferred, and proceed with the installation wizard.s
- 

## Pushing the User Profile to the Client PC

After AnyConnect 2.3 is installed, you should have the file “AnyConnectProfile.tmpl” in the folder C:\Documents and Settings\All Users\Application Data\Cisco\Cisco AnyConnect VPN Client\Profile. That is a template file you can rename with an .XML extension and then copy it to the FLASH on the ASA.

You can push the profile from security appliance to the client PC by specifying the CLI **group-policy webvpn-svc-profiles** <anyfilename.xml> command. In ASDM, select Configuration > Remote Access VPN > Network (Client) Access > Group Policies > Advanced > SSL VPN Client > Client Profile to Download.

Connect to the security appliance using the Client; the profile is pushed down to the client. Then disconnect, exit and restart the client. You see the checkbox “Auto reconnect” in the client preferences.

## Using the AnyConnect CLI Commands

The Cisco AnyConnect VPN Client provides a command line interface (CLI) for users who prefer to issue commands instead of using the graphical user interface. The following sections describe how to launch the CLI command prompt.

### For Windows

To launch the CLI command prompt and issue commands on a Windows system, locate the file *vpncli.exe* in the Windows folder C:\Program Files\Cisco\Cisco AnyConnect VPN Client. Double-click the file *vpncli.exe*.

### For Linux

To launch the CLI command prompt and issue commands on a Linux system, locate the file *vpn* in the folder */opt/cisco/vpn/bin/*. Execute the file *vpn*.

You can run the CLI in interactive mode, in which it provides its own prompt, or you can run it with the commands on the command line. [Table 5](#) shows the CLI commands.

**Table 5**      **AnyConnect Client CLI Commands**

Command	Action
<b>connect</b> <i>IP address or alias</i>	Client establishes a connection to a specific security appliance.
<b>disconnect</b>	Client closes a previously established connection.
<b>exit</b>	Exits the CLI interactive mode.
<b>help</b> or <b>?</b>	Gets usage information for CLI commands.
<b>hosts</b>	Lists all saved VPN server hosts.
<b>quit</b>	Exits the CLI interactive mode.
<b>state</b> or <b>status</b>	Displays current state of the VPN subsystem.
<b>stats</b>	Displays statistics about an established connection.
<b>version</b>	Displays the version of the currently installed Cisco AnyConnect VPN client.



#### Note

You cannot adjust preferences using the CLI interface of the AnyConnect client.

The following examples shows the user establishing and terminating a connection from the command line:

```
/opt/cisco/vpn/bin/vpn connect 1.2.3.4
```

Establishes a connection to a security appliance with the address *1.2.3.4*.

```
/opt/cisco/vpn/bin/vpn connect some_asa_alias
```

Establishes a connection to a security appliance by reading the profile and looking up the alias *some\_asa\_alias* in order to find its address.

```
/opt/cisco/vpn/bin/vpn stats
```

Displays statistics about the vpn connection.

```
/opt/cisco/vpn/bin/vpn disconnect
```

Disconnect the vpn session if it exists.

## Loading the AnyConnect Client and Configuring the Security Appliance with ASDM

Loading the client on the security appliance consists of copying a client image to the security appliance and identifying the file to the security appliance as a client image. With multiple clients, you must also assign the order that the security appliance loads the clients to the remote PC. Perform the following steps to install the client:

- 
- Step 1** Load the AnyConnect client images to the security appliance. On the ASDM toolbar, click **Configuration**. The navigation pane displays features to configure.
  - Step 2** In the navigation pane, click **Remote Access VPN**. The navigation pane displays VPN features.
  - Step 3** Choose **Network Access > Advanced > SSL VPN > Client Settings**. The SSL VPN Client Settings panel displays. (Figure 3).

This panel lists any AnyConnect client files that have been identified as AnyConnect client images. The order in which they appear in the table reflects the order that they download to the remote computer.

**Figure 3** *SSL VPN Client Settings Panel*



To add an AnyConnect client image, Click **Add** in the SSL VPN Client Images area. The Add SSL VPN Client Image dialog appears (Figure 4).

**Figure 4** *Add SSL VPN Client Image Dialog*



If you already have an image located in the flash memory of the security appliance, you can enter the name of the image in the Flash SVC Image field, and click **OK**. The SSL VPN Client Images panel now shows the AnyConnect client images you identified ([Figure 5](#)).

**Figure 5** *SSL VPN Client Panel with AnyConnect Client Images*



**Step 4** Click on an image name, and use the **Move Down** button to change the position of the image within the list.

This establishes the order in which the security appliance loads them to the remote computer. It loads the AnyConnect client image at the top of the list of images first. Therefore, you should move the image used by the most commonly-encountered operating system to the top of the list.

**Step 5** Enable the security appliance to download the AnyConnect client to remote users. Go to **Network Access > SSL VPN Connections**. The SSL VPN Connections panel appears ([Figure 6](#)). Check Enable SSL VPN client access for an interface.

**Figure 6**      *Enable SSL VPN Client Check Box*



- Step 6**      Configure a method of address assignment. You can use DHCP, and/or user-assigned addressing. You can also create a local IP address pool and assign the pool to a tunnel group.
- To create an IP address pool, choose **Network Access > Address Assignment > Address Pools**. Click **Add**. The Add IP Pool dialog appears ([Figure 7](#)).



**Figure 7**      **Add IP Pool Dialog**



- Step 7**      Enter the name of the new IP address pool. Enter the starting and ending IP addresses, and enter the subnet mask and click **OK**.
- Step 8**      Assign the IP address pool to a Connection (tunnel group). To do this, choose **Network (Client) Access > AnyConnect Connection Profiles**. The AnyConnect Connection Profiles panel appears ([Figure 8](#)):

**Figure 8**      *AnyConnect Connection Profiles Dialog Box*



Highlight a connection in the table, and click **Edit**. The Edit SSL VPN Connection dialog appears.

Click **Select** in the Client Address Assignment area. The Select Address Pool dialog appears ([Figure 9](#)), containing available address pools. Select a pool and click **OK**.

**Figure 9**      *Select Address Pool Dialog*



**Step 9**      Identify SSL VPN as a permitted VPN tunneling protocol for the group or user.

Choose **Network (Client) Access > Group Policies** from the navigation pane. Highlight the group policy in the Group Policy table, and click **Edit**.

The Edit Internal Group Policy dialog appears ([Figure 10](#)):

**Figure 10**      *Edit Internal Group Policy > General*



**Step 10** Check the **SSL VPN Client** check box to include SSL VPN as a tunneling protocol.

- Step 11** Configure SSL VPN features for a user or group. To display SSL VPN features for groups, In the navigation pane of the Internal Group Policy dialog, choose **Advanced > SSL VPN Client**. The SSL VPN Client features display [Figure 11](#).

**Figure 11** *SSL VPN Client Features*



- Step 12** Configure the following features on the SSL VPN Client panel:

**Keep Installer on Client System**—Enable to allow permanent client installation on the remote computer. Enabling disables the automatic uninstalling feature of the client. The client remains installed on the remote computer for subsequent connections, reducing the connection time for the remote user.

**Compression**—Compression increases the communications performance between the security appliance and the client by reducing the size of the packets being transferred.

**Datagram TLS**—Datagram Transport Layer Security (DTLS) allows the AnyConnect client establishing an SSL VPN connection to use two simultaneous tunnels—an SSL tunnel and a DTLS tunnel. Using DTLS avoids latency and bandwidth problems associated with some SSL connections and improves the performance of real-time applications that are sensitive to packet delays.

**Keepalive Messages**—Enter a number, from 15 to 600 seconds, in the Interval field to enable and adjust the interval of keepalive messages to ensure that an connection through a proxy, firewall, or NAT device remains open, even if the device limits the time that the connection can be idle. Adjusting the interval also ensures that the client does not disconnect and reconnect when the remote user is not actively running a socket-based application, such as Microsoft Outlook or Microsoft Internet Explorer.

**MTU**—Adjust the Maximum Transmission Unit (MTU) in bytes, from 256 to 1406 bytes. This setting affects only the AnyConnect client connections established in SSL, with or without DTLS. By default, the MTU size adjusts automatically based on the MTU of the interface that the connection uses, minus the IP/UDP/DTLS overhead.

**Client Profile to Download**—Specify a file on flash as a client profile. A profile is a group of configuration parameters that the CVC uses to configure the connection entries that appear in the client user interface, including the names and addresses of host computers.

**Optional Client Module to Download**—Specify any modules that the AnyConnect client needs to download to enable more features, such as Start Before Logon (SBL). To minimize download time, the CVC only requests downloads (from the security appliance) of core modules that it needs for each feature that it supports.

## Loading the AnyConnect Client and Configuring the Security Appliance with CLI

This section covers the following topics:

- [Loading the AnyConnect Client on page 38](#)
- [Enabling SSL VPN Connections on page 39](#)
- [Disabling Permanent Client Installation on page 42](#)
- [Prompting Remote Users on page 42](#)
- [Enabling AnyConnect Client Profile Downloads on page 43](#)
- [Enabling Rekey on page 44](#)
- [Enabling Start Before Logon for the AnyConnect Client on page 45](#)

### Loading the AnyConnect Client

Loading the client on the security appliance consists of copying a client image to the security appliance and identifying the file to the security appliance as a client image. With multiple clients, you must also assign the order that the security appliance loads the clients to the remote PC. Perform the following steps to install the client:

- Step 1** Copy the client image package to the security appliance using the **copy** command from privileged EXEC mode, or using another method. In this example, the images are copied from a tftp server using the **copy tftp** command:

```
hostname# copy tftp flash
Address or name of remote host []? 209.165.200.226
Source filename []? anyconnect-win-2.3.xxx-k9.pkg
Destination filename []? anyconnect-win-2.3.xxx-k9.pkg
Accessing
tftp://209.165.200.226/anyconnect-win-2.3.xxx-k9.pkg...!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!
Writing file
disk0:/cdisk71...!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!!
319662 bytes copied in 3.695 secs (86511 bytes/sec)
```

- Step 2** Identify a file on flash as a client package file using the **svc image** command from webvpn configuration mode:

**svc image** *filename order*

The security appliance expands the file in cache memory for downloading to remote PCs. If you have multiple clients, assign an order to the client images with the *order* argument.

The security appliance loads portions of each client in the order you specify until it matches the operating system of the remote PC. Therefore, assign the lowest number to the image used by the most commonly-encountered operating system. For example:

```
hostname(config-webvpn)# svc image windows.pkg 1
hostname(config-webvpn)# svc image linux.pkg 2
```



#### Note

The security appliance expands SSL VPN client and the Cisco Secure Desktop images in cache memory. If you receive the error message *ERROR: Unable to load SVC image - extraction failed*, use the **cache-fs limit** command to adjust the size of cache memory:

**Step 3** Check the status of the clients using the **show webvpn svc** command:

```
hostname(config-webvpn)# show webvpn svc
1. disk0:/windows.pkg 1
   CISCO STC win2k+ 1.0.0
   1,0,2,132
   Thu 06/22/2008 21:51:30.43

2. disk0:/linux.pkg 2
   CISCO STC linux 1.0.0
   1,0,0,164
   Thu 06/15/2008 20:09:22.43

2 SSL VPN Client(s) installed
```

## Enabling SSL VPN Connections

After installing the client, enable the security appliance to allow SSL VPN client connections by performing the following steps:

**Step 1** Enable clientless, browser-based connections on an interface using the **enable** command from webvpn configuration mode:

**enable interface**

For example:

```
hostname(config)# webvpn
hostname(config-webvpn)# enable outside
```

The following is an example for an IPv6 connection that enables IPv6 on the outside interface:

```
hostname(config)# interface GigabitEthernet0/0
hostname(config-if)# ipv6 enable
```

**Step 2** Enable SSL VPN connections globally using the **svc enable** command from webvpn configuration mode.

For example:

```
hostname(config-webvpn)# svc enable
```

**Step 3** Configure a method of address assignment. You can use DHCP, and/or user-assigned addressing. You can also create a local IP address pool using the **ip local pool** command from global configuration mode:

**ip local pool** *poolname startaddr-endaddr mask mask*

The following example assumes the authentication server group is LOCAL. The example creates the local IP address pool *vpn\_users*:

```
hostname(config)# ip local pool vpn_users 209.165.200.225-209.165.200.254
mask 255.255.255.224
```

- Step 4** Assign IP addresses to a tunnel group. One method you can use to do this is to assign a local IP address pool with the **address-pool** command from general-attributes mode:

**address-pool** *poolname*

To do this, first enter the **tunnel-group name general-attributes** command to enter general-attributes mode. Then specify the local IP address pool using the **address-pool** command.

In the following example, the user configures the existing tunnel group *telecommuters* to use the address pool *vpn\_users* created in step 3:

```
hostname(config)# tunnel-group telecommuters general-attributes
hostname(config-tunnel-general)# address-pool vpn_users
```

- Step 5** Assign a default group policy to the tunnel group with the **default-group-policy** command from tunnel group general attributes mode:

**default-group-policy** *name*

In the following example, the user assigns the group policy *sales* to the tunnel group *telecommuters*:

```
hostname(config-tunnel-general)# default-group-policy sales
```

- Step 6** Create and enable a group alias that displays in the group list on the login page using the **group-alias** command from tunnel group webvpn attributes mode:

**group-alias** *name enable*

First exit to global configuration mode, and then enter the **tunnel-group name webvpn-attributes** command to enter tunnel group webvpn attributes mode.

In the following example, the user enters webvpn attributes configuration mode for the tunnel group *telecommuters*, and creates the group alias *sales\_department*:

```
hostname(config)# tunnel-group telecommuters webvpn-attributes
hostname(config-tunnel-webvpn)# group-alias sales_department enable
```

- Step 7** Enable the display of the tunnel-group list on the login page from webvpn mode:

**tunnel-group-list** *enable*

First exit to global configuration mode, and then enter webvpn mode.

In the following example, the user enters webvpn mode, and then enables the tunnel group list:

```
hostname(config)# webvpn
hostname(config-webvpn)# tunnel-group-list enable
```

- Step 8** Specify SSL as a permitted VPN tunneling protocol for the group or user with the **vpn-tunnel-protocol svc** command in group-policy mode or username mode:

**vpn-tunnel-protocol** *svc*



To do this, first exit to global configuration mode, enter the **group-policy name attributes** command to enter group-policy mode, or the **username name attributes** command to enter username mode, and then enter the **webvpn** command to enter webvpn mode and change the settings for the group or user.

The following example identifies SSL as the only permitted tunneling protocol for the group-policy *sales*:

```
hostname(config)# group-policy sales attributes
hostname(config-group-policy)# webvpn
hostname(config-group-webvpn)# vpn-tunnel-protocol svc
```

For more information about assigning users to group policies, see *Cisco Security Appliance Command Line Configuration Guide*, Chapter 30, “Configuring Tunnel Groups, Group Policies, and Users.”

## Enabling IPv6 Connections

The AnyConnect client allows access to IPv6 resources over a public IPv4 connection (only for Windows XP SP2, Windows Vista, Mac OS X, and Linux). You must use the command line interface to configure IPv6 access. ASDM does not support IPv6.

You enable IPv6 access using the **ipv6 enable** command as part of enabling SSL VPN connections. The following is an example for an IPv6 connection that enables IPv6 on the outside interface:

```
hostname (config)# interface GigabitEthernet0/0
hostname (config-if)# ipv6 enable
```

To enable IPv6 SSL VPN, do the following general actions:

1. Enable IPv6 on the outside interface.
2. Enable IPv6 and an IPv6 address on the inside interface.
3. Configure an IPv6 address local pool for client-assigned IP addresses.
4. Configure an IPv6 tunnel default gateway.

To implement this procedure, do the following steps:

### Step 1 Configure Interfaces:

```
interface GigabitEthernet0/0
    nameif outside
    security-level 0
    ip address 192.168.0.1 255.255.255.0
    ipv6 enable ; Needed for IPv6.
!
interface GigabitEthernet0/1
    nameif inside
    security-level 100
    ip address 10.10.0.1 255.255.0.0
    ipv6 address 2001:DB8::1/32 ; Needed for IPv6.
    ipv6 enable ; Needed for IPv6.
```

### Step 2 Configure an 'ipv6 local pool' (used for AnyConnect Client IPv6 address assignment):

```
ipv6 local pool ipv6pool 2001:DB8:1:1::5/32 100 ; Use your IPv6 prefix here
```



**Note** You still need to configure an IPv4 address pool when using IPv6 (using the `ip local pool` command)

**Step 3** Add the ipv6 address pool to your Tunnel group policy (or group-policy):

```
tunnel-group YourTunGrp1 general-attributes ipv6-address-pool ipv6pool
```



**Note** Again, you must also configure an IPv4 address pool here as well (using the 'address-pool' command).

**Step 4** Configure an IPv6 Tunnel Default Gateway:

```
ipv6 route inside ::/0 X:X:X:X::X tunneled
```

## Disabling Permanent Client Installation

Disabling permanent AnyConnect client installation disables the automatic uninstalling feature of the client. The client remains installed on the remote computer for subsequent connections, reducing the connection time for the remote user.

To disable permanent AnyConnect client installation for a specific group or user, use the **svc keep-installer** command from group-policy or username webvpn modes:

```
svc keep-installer none
```

The default is that permanent installation of the client is enabled. The client on the remote computer stays installed at the end of every session. The following example configures the existing group-policy *sales* to not keep the client installed on the remote computer:

```
hostname(config)# group-policy sales attributes
hostname(config-group-policy)# webvpn
hostname(config-group-policy)# svc keep-installer none
```

## Prompting Remote Users

You can enable the security appliance to prompt remote SSL VPN client users to download the client with the **svc ask** command from group policy webvpn or username webvpn configuration modes:

```
[no] svc ask {none | enable [default {webvpn | svc} timeout value]}
```

**svc ask enable** prompts the remote user to download the client or go to the portal page for a clientless connection and waits indefinitely for user response.

**svc ask enable default svc** immediately loads the client.

**svc ask enable default webvpn** immediately goes to the portal page.

**svc ask enable default svc timeout value** prompts the remote user to download the client or go to the portal page and waits the duration of *value* before taking the default action—downloading the client.

**svc ask enable default webvpn timeout value** prompts the remote user to download the client or go to the portal page, and waits the duration of *value* before taking the default action—displaying the portal page.

Figure 12 shows the prompt displayed to remote users when either **default svc timeout** *value* or **default webvpn timeout** *value* is configured:

**Figure 12** Prompt Displayed to Remote Users for SSL VPN Client Download



The following example configures the security appliance to prompt the remote user to download the client or go to the portal page and to wait 10 seconds for user response before downloading the client:

```
hostname(config-group-webvpn)# svc ask enable default svc timeout 10
```

## Enabling AnyConnect Client Profile Downloads

An AnyConnect client profile is a group of configuration parameters, stored in an XML file, that the client uses to configure the connection entries that appear in the client user interface. The client parameters (XML tags) include the names and addresses of host computers and settings to enable additional client features.

You can create and save XML profile files using a text editor. The client installation contains one profile template (AnyConnectProfile.tmpl) that you can edit and use as a basis to create other profile files.

The profile file is downloaded from the security appliance to the remote user's PC, so you must first import the profile(s) into the security appliance in preparation for downloading to the remote PC. You can import a profile using either ASDM or the command-line interface. See Appendix A of the *Cisco AnyConnect VPN Client Administrator Guide* for a sample AnyConnect profile.

When the AnyConnect client starts, it reads the *anyfilename.xml* file in the following directory:

C:\Documents and Settings\<your\_username>\Application Data\Cisco\Cisco AnyConnect VPN Client.

The AnyConnect client stores data that the user previously entered, such as the username and the security appliance IP address/hostname from the last successful connection. The client then establishes an initial connection to the security appliance to get the list of tunnel groups to display in the GUI. During this initial connection, if the security appliance is no longer accessible or if the hostname cannot be resolved, the user sees the message, "Connection attempt has failed" or "Connection attempt has failed due to unresolvable host entry."

You can place a copy of your profile (for example, CiscoAnyConnectProfile.xml) in the directory:

C:\Documents and Settings\All Users\Application Data\Cisco\Cisco AnyConnect VPN Client\Profile

The location for Windows Vista is slightly different: C:\ProgramData\Cisco\Cisco AnyConnect VPN Client\Profile. The host that appears in the Connect to combo box is the first one listed in the profile or the last host you successfully connected with. This is a way to test a potential client profile.

For more information about editing AnyConnect client profiles, see the *Cisco AnyConnect VPN Client Administrator Guide*.

After you create an AnyConnect client profile, follow these steps to enable the security appliance to download them to remote AnyConnect client users:

- Step 1** Identify to the security appliance an AnyConnect client profiles file to load into cache memory using the **svc profile** command from webvpn configuration mode:

```
[no] svc profiles {value profile | none}
```

This command makes profiles available to group policies and username attributes of AnyConnect client users.

In the following example, the user previously created two new profile files (sales\_hosts.xml and engineering\_hosts.xml) from the cvcprofile.xml file and loaded them to the flash memory.

Now the user specifies these files as AnyConnect client profiles for use by group policies, specifying the names *sales\_hosts* and *engineering\_hosts*:

```
asa1(config-webvpn)# svc profiles sales disk0:/sales_hosts.xml
asa1(config-webvpn)# svc profiles engineering disk0:/engineering_hosts.xml
```

Entering the **dir cache:stc/profiles** command shows the profiles loaded in cache memory:

```
asa1(config-webvpn)# dir cache:/stc/profiles

Directory of cache:stc/profiles/

0      ----  774          11:54:41 Oct 22 2008 engineering.xml
0      ----  774          11:54:29 Oct 22 2008 sales.xml

2428928 bytes total (18219008 bytes free)
asa1(config-webvpn)#
```

- Step 2** Enter group policy webvpn or username attributes webvpn configuration mode and specify a profile for the group or user with the **svc profiles** command:

```
[no] svc profiles {value profile | none}
```

In the following example, the user follows the **svc profiles value** command with a question mark (?) to query the security appliance so see the available profiles. Then the user configures the group policy to use the AnyConnect client profile *sales*:

```
asa1(config-group-webvpn)# svc profiles value ?

config-group-webvpn mode commands/options:
Available configured profile packages:
  engineering
  sales
asa1(config-group-webvpn)# svc profiles sales
```

## Enabling Rekey

When the security appliance and the AnyConnect client perform a rekey, they renegotiate the crypto keys and initialization vectors, increasing the security of the connection.

To enable the client to perform a rekey on an SSL VPN connection for a specific group or user, use the **svc rekey** command from group-policy and username webvpn modes.

```
[no] svc rekey {method {new-tunnel | none | ssl} | time minutes}
```

**method new-tunnel** specifies that the client establishes a new tunnel during rekey.

**method none** disables rekey.

**method ssl** specifies that SSL renegotiation takes place during rekey.

**time** *minutes* specifies the number of minutes from the start of the session until the rekey takes place, from 1 to 10080 (1 week).

In the following example, the client is configured to renegotiate with SSL during rekey, which takes place 30 minutes after the session begins, for the existing group-policy *sales*:

```
hostname(config)# group-policy sales attributes
hostname(config-group-policy)# webvpn
hostname(config-group-policy)# svc rekey method ssl
hostname(config-group-policy)# svc rekey time 30
```

## Enabling or Disabling DTLS

Datagram Transport Layer Security (DTLS) allows the AnyConnect client establishing an SSL VPN connection to use two simultaneous tunnels—an SSL (TLS) tunnel and a DTLS tunnel. DTLS requires the TLS tunnel for a number of reasons, including protocol negotiation and fallback technologies. Using DTLS avoids latency and bandwidth problems associated with some SSL connections and improves the performance of real-time applications that are sensitive to packet delays.

DTLS is enabled implicitly when you enable the interface. If you decide to disable DTLS, SSL VPN connections connect with an SSL VPN tunnel only.

Use the following command options to enable an interface with DTLS or just with TLS:

You can enable DTLS for all AnyConnect client users with the **dtls enable** command in webvpn configuration mode:

```
[no] enable interface | tls-only }
```

For example, to enable the outside interface with DTLS, enter the following:

```
hostname(config-webvpn)# enable outside
```

To disable DTLS and allow only TLS, enter the following command instead:

```
hostname(config-webvpn)# enable outside tls-only
```

You can enable DTLS or TLS on a per-user or per-group basis.



### Note

When using the AnyConnect VPN client with DTLS on an ASA device Dead Peer Detection (DPD) must be enabled in the group policy on the ASA to allow the AnyConnect client to fall back to TLS, if necessary. Fallback to TLS occurs if the AnyConnect client cannot send data over the UDP/DTLS session, and DPD is the mechanism necessary for fallback to occur.

## Enabling Start Before Logon for the AnyConnect Client

To minimize download time, the AnyConnect client requests downloads (from the security appliance) only of core modules that it needs for each feature that it supports. To enable new features, such as Start Before Logon (SBL), you must specify the module name using the **svc modules** command from group policy webvpn or username webvpn configuration mode:

```
[no] svc modules {none | value string }
```

The *string* for SBL is **vpngina**

In the following example, the user enters group-policy attributes mode for the group policy *telecommuters*, enters webvpn configuration mode for the group policy, and specifies the string *vpngina* to enable SBL:

```
hostname(config)# group-policy telecommuters attributes
hostname(config-group-policy)# webvpn
hostname(config-group-webvpn)# svc modules value vpngina
```

In addition, the administrator must ensure that the AnyConnect <anyfilename.xml> profile has the <UseStartBeforeLogon> statement set to true. For example:

```
<UseStartBeforeLogon UserControllable="false">true</UseStartBeforeLogon>
```

The system must be rebooted before Start Before Logon takes effect.

For more information about editing AnyConnect client profiles, see the *Cisco AnyConnect VPN Client Administrator Guide*.

**Note**

On Systems prior to Windows Vista, Start Before Logon works only for PCs that are part of a domain and not part of a workgroup or working standalone.

## CSA Interoperability with the AnyConnect Client and Cisco Secure Desktop

If your remote users have Cisco Security Agent (CSA) installed, you must import new CSA policies to the remote users to enable the AnyConnect VPN Client and Cisco Secure Desktop to interoperate with the security appliance.

To do this, follow these steps:

- 
- Step 1** Retrieve the CSA policies for the AnyConnect client and Cisco Secure Desktop. You can get the files from:
- The CD shipped with the security appliance.
  - The software download page for the ASA 5500 Series Adaptive Security Appliance at <http://www.cisco.com/cgi-bin/tablebuild.pl/asa>.

The filenames are AnyConnect-CSA.zip and CSD-for-CSA-updates.zip

- Step 2** Extract the .export files from the .zip package files.
- Step 3** Choose the correct version of the .export file to import. The Version 5.2 export files work for CSA Versions 5.2 and higher. The 5.x export files are for CSA Versions 5.0 and 5.1.
- Step 4** Import the file using the Maintenance > Export/Import tab on the CSA Management Center.
- Step 5** Attach the new rule module to your VPN policy and generate rules.

For more information, see the CSA document *Using Management Center for Cisco Security Agents 5.2*. Specific information about exporting policies is located in the section *Exporting and Importing Configurations*.

---

## Uninstalling the Cisco AnyConnect VPN Client

To manually uninstall the AnyConnect client from a Windows system, use the standard “Add or Remove Programs” Control Panel available from the Start menu.

The procedure for manually uninstalling the AnyConnect client from a Linux or Mac OS X system is the same for both systems. As root, run the following shell script:

```
/opt/cisco/vpn/bin/vpn_uninstall.sh
```

Typically, you would do this via sudo, as follows:

```
$ sudo /opt/cisco/vpn/bin/vpn_uninstall.sh
```

If you do not use sudo, use a root shell:

```
# /opt/cisco/vpn/bin/vpn_uninstall.sh
```

## Usage Notes

This section lists known interoperability considerations and other issues to consider before installing and using the Cisco AnyConnect VPN Client, Release 2.3.2016 and earlier releases.

### Vista Routing and Remote Access Service Incompatibility

The Routing and Remote Access Service on a client PC running Vista prevents AnyConnect from updating the Windows IP Forwarding (routing) table to direct network traffic to the VPN connection. A Cisco AnyConnect VPN Client window displays the following message:

The Windows Routing and Remote Access service is not compatible with the VPN client. The VPN client cannot operate correctly when this service is running.

To open the window required to disable this service, choose **Start > Control Panel > Administrative Tools > Services > Routing and Remote Access Service**.

### PC with Faulty Driver Blue-screens after AnyConnect Authentication

PCs sometimes crash after AnyConnect authentication if they are running Microsoft Windows XP with SP2 and the faulty Microsoft driver ushbus.sys (Default Hub Driver for USB, v5.1.2600.3020). To prevent the problem, users may do either of the following:

- Upgrade to XP SP3.
- Go to [Stop error when you resume a computer that is running Windows XP or a 64-bit version of Windows Server 2003 from hibernation: "STOP 0x1000007E"](#) to install the Microsoft hotfix.

### vpncli Process Exits During an Upgrade and Is Not Relunched

By design, any process that needs to be upgraded is terminated so that the upgrade can complete. If the process is the CLI (vpncli), then the process is not relaunched. The command shell might also exit, depending on the configuration of the default behavior of the command shell on a particular OS.

### XML Profile Enhancement for Selecting Windows Certificate Store

In Release 2.3.185 and later releases, administrators can control which certificate store AnyConnect uses for locating certificates. This applies only to the AnyConnect client on Windows.

Windows provides separate certificate stores for the local machine and for the current user. Users with administrative privileges on the computer will have access to both stores. The original AnyConnect behavior was to load certificates from all available certificate stores. An ASA administrator may want to configure AnyConnect via XML profile to restrict certificate lookups to only the user store or only the machine store.

To this end, a new setting called `CertificateStore` has been added to the `ClientInitialization` element in the XML profile. It has three possible (case-sensitive) values: `All` (default), `Machine`, or `User`.

**Note**

The default setting (`All`) is appropriate for the majority of cases. Do not change this setting unless you have a specific reason or scenario requirement to do so.

If the `CertificateStore` setting is not in the profile, AnyConnect uses all available certificate stores. This setting has no effect on non-Windows platforms.

Within the `ClientInitialization` section of the XML template, you can specify the certificate store that you want to use. Possible values are as follows:

- `All`—(default) All certificates are acceptable.
- `Machine`—Use the machine certificate.
- `User`—Use a user-generated certificate.

**Note**

These attributes are case-sensitive.

## Certificate Enrollment Prompts Can Occur Twice

Internet Explorer (IE) attempts to access the user certificate store when one establishes a browser-based VPN connection. With `Start Before Logon`, AnyConnect attempts to access the machine certificate store because user login credentials are not yet present. Because Internet Explorer cannot access the machine certificate store, users who use `WebLaunch` to start AnyConnect, or use `Start Before Logon` may be prompted to enroll first by Internet Explorer for a user certificate and later by AnyConnect for a machine certificate; however, the prompts do not specify the type of certificate store accessed.

## AnyConnect Client Setup Flow

The following section is an example of the AnyConnect client setup flow. In this example, there is one tunnel session.

- There can be up to two channels associated with the one tunnel session (TLS and DTLS).
- TLS is always established as the first channel and this channel remains active for the entire tunnel session.

TLS is established in two phases:

1. **Authentication phase**—The authentication phase uses core components of the OS, for example WinInet on Windows. This phase uses the cryptographic protocols available to the OS; for example, AES is only available on Vista or later, therefore, you must configure the Secure Gateway to use the protocols that allow the authentication phase to succeed.



2. Tunneling phase—When the authentication phase is complete, the tunneling phase begins. This phase uses the strongest possible cryptography offered by the Secure Gateway configuration; therefore, if the Secure Gateway has configured:

AES-256-SHA1; 3DES-MD5, RC4-MD5

The tunneled data uses AES-256-SHA1.



#### Note

Because platforms such as Windows XP do not support AES in WinInet, the addition of 3DES-MD5 as an alternative cryptographic suite is needed to complete the initial authentication phase.

When the TLS channel is active, tunneled data immediately flows over the TLS channel.

AnyConnect then attempts to fall-forward to the preferable DTLS channel if the headend allows this configuration.

AnyConnect also falls back from DTLS to TLS at any time if the DTLS channel DPD indicates a loss of communication.

Control data *always* flows down the TLS channel (there are also separate DPDs and svc-keepalives for both channels).



#### Note

There is some degree of TLS traffic that is compressed for all tunnel types, whether doing DTLS or solely TLS.

## Using the AT&T Aircard with Cisco AnyConnect VPN Client

When using the AT&T Aircard with Cisco AnyConnect VPN client, if you encounter problems, use the AT&T Communications Manager to uncheck **Use Rules Engine** in version 6.7 of the AT&T client or **Use Connection Maintenance** in the 6.2 version.

## Usage Notes for AnyConnect VPN Client Release 2.3

The following usage notes are specifically for Release 2.3.

### Split-Exclude Tunneling Requires Enabling AllowLocalLanAccess in the AnyConnect Client

Split-Exclude Tunneling Requires Enabling AllowLocalLanAccess in the AnyConnect Client. All split-exclude tunneling is regarded as local LAN access. To use the exclude feature of split-tunneling, you must enable the AllowLocalLanAccess preference in the AnyConnect VPN Client preferences. By default, local LAN access is disabled. This behavior is different from that of AnyConnect Client Release 2.2.

To allow local LAN access, and therefore split-exclude tunneling, a network administrator can enable it in the profile, or users can enable it in their preferences settings. To allow local LAN access, a user selects the “Allow Local LAN access” check box if split-tunneling is enabled on the secure gateway and is configured with the “split-tunnel-policy exclude specified” policy.

## AutoReconnectBehavior Preference Defaults to DisconnectOnSuspend

The AutoReconnectBehavior preference defaults to DisconnectOnSuspend. This behavior is different from that of AnyConnect Client Release 2.2. For reconnect after resume, the network administrator must either set ReconnectAfterResume in the profile or make the AutoReconnect and AutoReconnectBehavior preferences user controllable in the profile to allow users to set it.

## Using Virtualization Software over a Tunnel with AnyConnect.

To connect to resources on the private side of the secure gateway using virtualization technologies, configure the virtual machine on your PC to use NAT for the networking configuration. This allows tunneling of the Virtual Machine traffic over the AnyConnect tunnel.

## Microsoft Java is Not Supported from the AnyConnect WebLaunch

The AnyConnect client no longer supports Microsoft Java from the AnyConnect WebLaunch. To use WebLaunch, Windows end-systems must have either ActiveX enabled or Sun Java version 1.4 or higher installed.

## AnyConnect 2.3 Supports DEP Option

On Windows Vista, on any hardware, DEP is on by default for all AnyConnect processes. For Windows 2003 and Windows XP, this is true if the hardware processor supports DEP. See <http://support.microsoft.com/default.aspx?scid=kb;en-us;875352> for more details.

## Avoiding Installation of an ActiveX Control in Pre-deployment Scenarios

In pre-deploy scenarios, if you intend to use only standalone mode and/or you do not want the ActiveX control to be installed on a system, you can do one of the following operations:

- Create an MSI transform to set the ActiveX property to disabled (NOINSTALLACTIVEX=1)
- Invoke the installer as follows: `MSIExec /i anyconnect-win-n.n.n-pre-deploy-k9.msi NOINSTALLACTIVEX=1`

where n.n.n is the actual version that is being installed.

## Usage Notes From Earlier Releases

The following usage notes from earlier releases also apply to the AnyConnect client Release 2.3.

## Network Connections Control Panel Might Show Generic Adapter Name

The name of the adapter that AnyConnect adds to Windows (as shown in the Network Connections control panel) might be marked with the generic name “Local Area Connection *n*”, where *n* is a number (for example, Local Area Connection 6). The Windows operating system sets this generic name when the adapter is installed. The AnyConnect client code attempts to update this name to “Cisco AnyConnect VPN Client Connection” each time a VPN session starts. If an upgrade occurs during Start Before Login (SBL), then the attempt to change the name of the AnyConnect adapter might fail. In this case, the generic name appears in the operating system’s Network Connections control panel. The next time a VPN is established (after the SBL-initiated session disconnects), the name should be properly updated.

This is a cosmetic issue (due to a limitation in the operating system) that affects only the name displayed in the Windows Network Connections control panel. An upgrade during SBL is the only known cause for this issue.

## QoS Policing Does Not Apply to AnyConnect Connections

Quality of Service policing does not apply to AnyConnect client connections. Attempting to do this results in an error message.

## Network Subsystem on Windows Vista Might Become Unresponsive During Sleep/Resume Cycles or Other High-load Conditions (KB-952876)

If you use sleep and resume on Vista, you might find that the tunnel cannot be established due to the AnyConnect driver not being enabled. A reboot is typically required to recover from this condition.

The problem is caused by an issue in the Vista Kernel component as described in KB-952876 (<http://support.microsoft.com/kb/952876>). When this issue occurs, another core Vista component, TCPIPREG.sys, fails to function. The Cisco AnyConnect VPN Client relies on this service to set the IP address of the Virtual Adapter. If you see an error stating that the Virtual Adapter could not be set up, you might have encountered this issue. We recommend that you apply the patch if you are experiencing issues on Vista where the AnyConnect adapter fails to enable. After applying the patch, you might still see an occasional failure due to a timing issue in the TCPIPREG.sys service. This is rare and should be recoverable by simply trying the tunnel a second time. Cisco is working with Microsoft to correct this remaining issue.

## AnyConnect Client over Proxies

AnyConnect supports connections to the security appliance via a proxy server that uses Basic and NTLM authentication. Socks proxies are not supported. DTLS (using UDP) is not supported if the proxy server runs only TCP.

Additionally, on Windows only, you can also use authenticating proxies that use Basic or NTLM for authorization. If you have Internet Explorer configured with a proxy, you must activate the “Use HTTP 1.1 through proxy connections” setting in the advanced Internet Explorer settings to use the AnyConnect client. If this option is not set, the AnyConnect client connection does not come up.

In Internet Explorer, choose Internet Options from the Tools menu. Click the Advanced tab, and under the HTTP 1.1 Settings, check “Use HTTP 1.1 through proxy connections.”

## WINS and DNS

The AnyConnect client supports group-policy configured primary and secondary Windows Internet Naming Services (WINS) or Domain Naming Services (DNS).

## SSL VPN Clients Do Not Support Split DNS

Neither the AnyConnect client nor the older SSL VPN client (which the AnyConnect client replaces) supports split DNS. With either of these types of SSL VPN connection, when split DNS is enabled, regardless of whether the platform is the security appliance, VPN3000 Concentrator, or IOS, all DNS queries are sent through the tunnel. Only the Cisco VPN Client (IPsec) supports Split DNS.

## Setting the Secure Connection (Lock) Icon

The Lock icon indicates a secure connection. XP automatically hides this icon among those that have not been recently used. The end user can prevent XP from hiding this icon as follows:

- 
- Step 1** Go to the taskbar where the tray icons are displayed and right click the left angle bracket ( < ).
  - Step 2** Select “Customize Notifications...”
  - Step 3** Select “Cisco Systems AnyConnect VPN Client” and set to “Always Show.”
- 

## Cisco Security Agent Version Requirements

Cisco Security Agent (CSA) Version 4.5 and higher is the only version compatible with the AnyConnect client. The appropriate CSA policy ships with CSA and is attached to the group “Remote desktops and laptops.” These policies are not enabled by default; you must select them to prevent the AnyConnect client from failing with CSA version 4.5.

## PC Wireless Client Configurations

If a client wireless adapter profile supports scanning for a better access point, and you use the Cisco AnyConnect VPN Client or Cisco VPN Client (IPsec) with that profile, disable such scanning. These scans can cause disconnections or stall traffic on the tunnel. To support scanning for non-SSL/IPsec connections, create another profile.

## Certificate Revocation List Processing

A Certificate Revocation List (CRL) contains a number of certificate serial numbers that have been revoked. The client downloads this list from a CRL server and looks up the certificate of the security appliance in the list.

The Cisco AnyConnect VPN Client requires a Certificate Revocation key with a value of 1 to enable the checking of the certificate revocation list. The following path shows the Certificate Revocation key and value on the remote PC:

My Computer | HKEY\_USERS | <Secure ID\_of\_Logged\_User> | Software | Microsoft | Windows | CurrentVersion | CertificateRevocation REG\_DWORD 0x00000001

The client attempts to read the value of the flag *CertificateRevocations* shown above to determine whether the client checks for revocation of the security appliance certificate.

To set the Revocation flag, select **Control Panel > Internet Options**. Click the **Advanced** tab, and click the **Restore Defaults** button near the bottom of the window. This option restores all of the options under the Advanced tab to the original settings.

Alternatively, to avoid restoring original settings, you can perform the following:

- 
- Step 1** Check the check-box **Check for server certificate revocation** (requires restart).
  - Step 2** Click **Apply**.

- Step 3** Click **OK**.
- Step 4** Restart Windows.
- 

If Revocation is enabled, a dialog window prompts the remote user to accept or deny the certificate that has a revocation error.

## Dynamic Install Fails on Windows Vista When Running Low-rights Internet Explorer

Internet Explorer 7 on Windows Vista has a new security feature called Low Rights Internet Explorer. This feature changes the rights of the sandbox that the browser operates from to the lowest level possible. Because Windows Installer service has the ability to elevate all the way to Local System, the Windows Installer refuses to accept calls from Low Rights processes (as IE7 now is).

When using low-rights Internet Explorer to attempt a first-time web installation of the AnyConnect client, the MSI install fails immediately. The MSI log contains the following entry:

Failed to connect to server. Error: 0x80070005

To avoid this, users on Vista *must* add the Secure Gateway to the Trusted Zone.

## AnyConnect Fails to Establish a DTLS Tunnel When Using RC4-MD5 Encryption

When the ASA to which the AnyConnect client is attempting to connect is configured to only do RC4-MD5 encryption, the client is unable to establish a DTLS tunnel.

## msvcp60.dll Must Be Available for Installation of the AnyConnect Client

To use the Cisco AnyConnect VPN Client, you must have the file msvcp60.dll — c++ runtime located in the winnt\system32 directory on your system. This dll is likely already to be present on most images, since installing other products (such as Office 2000) results in this file being placed on the system.

Because of this common practice, this dll file is excluded to reduce the image size for AnyConnect client dynamic installations. For more information about this problem, see the Microsoft Knowledge Base, article 259403, at <http://support.microsoft.com/kb/259403>.

## Secure VPN Via Windows Remote Desktop Is Supported

The AnyConnect VPN Client, Release 2.2 and higher, supports VPN connection establishment via a Windows Remote Desktop session. If you connect to the PC via Remote Desktop, your VPN connection will be allowed.

## AnyConnect Start Before Logon GINA Might Not Appear on Login Screen after Reboot

When the AnyConnect Start Before Logon GINA is installed on a user's PC using the standalone installer (WinGinaSetup-xxxx.msi), the GINA does not appear on the login screen after a reboot. This occurs because the AnyConnect GINA requires that the following be installed:

- AnyConnect Client
- An AnyConnect profile (*anyfilename.xml* file) in Documents and Settings/All Users/Application Data/Disco/CiscnyConnect VPN Client/Profile/ with the following line in it:

```
<UseStartBeforeLogon UserControllable="false">true</UseStartBeforeLogon>
```

Network administrators must push out a profile using their SMS or other software deployment engine along with the MSI files if they want to perform a preinstall of the profile.

## When Using a Client-Side Proxy and Full Tunneling, the Proxy Should Be Reset

When a client side proxy is used to connect to the Internet, full tunneling cannot not be enforced on the client since users can still connect to the proxy server even when in full tunneling mode. This behavior inherent in the nature of SSL VPN solutions.

To work around this issue, set the VPN connection MSIE configuration settings on the secure gateway to “no proxy” rather than “do not change proxy settings.” This will cause the client to remove the “public side” proxy settings from MSIE, while the VPN connection is established. Then, browser and other Windows Internet traffic goes over the tunnel.

## Linux-Specific AnyConnect Client Issue

The AnyConnect client might not establish DTLS tunnel in Linux and might revert to TLS.

In addition, the AnyConnect client reports that statistics in the Linux user interface are not available. Closing the user interface without disconnecting and launching another (while the tunnel is still active) seems to fix the problem.

## Setting the AnyConnect Pre-Login Banner

The pre-login banner is the optional banner message that appears in line with the end-user AnyConnect client interface. You can use either of the following methods to configure the banner on the security appliance:

- Import/export the DfltCustomization file <custom> <auth-page>.

```
<copyright-panel>
<mode>enable</mode>
<text>Copyright...</text>
<copyright-panel>
```

The <text> element value is the pre-banner text.

- Select ASDM.Remote Access VPN > Clientless SSL VPN Access > Portal > Customization. On the resulting window, select DfltCustomization, and then Edit. A GUI appears, and you can edit the Copyright text.

## AnyConnect Requires That the ASA Be Configured to Accept TLSv1 Traffic

The AnyConnect client cannot establish a connection with the following ASA settings for “ssl server-version”:

- ssl server-version sslv3.
- ssl server-version sslv3-only.

## Smartcards Supported

The AnyConnect client supports Aladdin eTokenPro32k and Axalto Smartcards and readers on Windows Vista Ultimate, Windows XP Professional with SP2 and Windows 2000 Professional with SP4, as well as for Mac OS X Versions 10.4 and 10.5. In Release 2.3, there is no Smartcard support for Linux.

## IPv6 AnyConnect Failover is Not Supported for the Security Appliance

ASA Releases 8.0 and 8.1 do not support IPv6 failover, so failover of IPv6 AnyConnect (as well as failover of clientless SSL VPN) sessions is also not supported.

## RADIUS Interim Accounting Update Feature

In conjunction with ASA Release 8.0.3.1 and higher, the AnyConnect client now supports interim accounting for a VPN connection running simultaneous SSL VPN Clientless and AnyConnect sessions.

This is especially important for SSO integration with the NAC appliance, where NAC requires the Accounting Start request to contain the Frame-IP-Address.

Previously, if an AnyConnect session was launched from a browser and not the standalone AnyConnect GUI, the Clientless session (with no concept of Frame-IP) would send the Accounting Start request without it, and NAC-SSO would fail as a result.

To enable this feature, enable the new CLI command **interim-accounting-update** under **aaa-server** on the security appliance.

## AnyConnect Split-tunneling Works on Windows Vista

In the AnyConnect client, Release 2.1 and higher, split-tunneling works correctly with Windows XP, Windows 2000, *and* Windows Vista.

## Selecting Crypto Toolkits for AnyConnect on Windows Platforms

To use Windows certificates and proxy support, the AnyConnect client uses the cryptography support present on the operating system to establish an authentication session. The cryptographic cipher used for authentication is bounded by what the host operating system supports and is distinct from the cipher used to encrypt the AnyConnect tunnel data.

This is commonly encountered when an administrator configures “ssl encryption aes128-sha1” on the security appliance. Because older versions of Windows (pre-Vista) do not support AES, neither Internet Explorer nor the AnyConnect client in stand-alone mode can establish clientless or AnyConnect sessions on these platforms when *only* AES is configured.

Since the AnyConnect client always attempts to use the strongest tunnel encryption possible, it is possible to work around this by using “ssl encryption aes128-sha1 3des-sha1”. This causes the initial authentication session to use triple DES, but causes all tunneled data to be encrypted with AES.

## First User Message for Double-byte Languages Does Not Translate Correctly

With the Unicode version of the AnyConnect VPN Client—which allows for double-byte languages such as Japanese, Chinese, and so on—the first user message to appear does not correctly translate, because that message is missing from the AnyConnect translation table.

To work around this problem, add the following lines to the translation table file that you are using for translations:

```
msgid "Please enter your username and password."
msgstr ""
```

The message string (msgstr) value should be your translation of the English string in msgid.

## Ensuring Reliable DTLS (UDP) Connections Through Third-Party Firewalls

A third-party network firewall blocks DTLS (UDP) traffic if traffic is idle for 40 seconds and if DTLS keepalive is not enabled.

When a third-party network firewall is located between the client PC and the security appliance, the firewall inspects each DTLS packet and makes a decision whether to pass the packet along to the destination. If there has been an idle period of DTLS traffic, the firewall might stop sending data to the client or security appliance.

A customer has observed that the default behavior of a third-party firewall in their network results in the DTLS (UDP) traffic being dropped after an idle period of 40 seconds. This occurs when the DTLS keepalive is not configured, or is configured with a value that is greater than the timeout interval of the third-party firewall.

By default, the DTLS keepalive is disabled.

When the firewall stops DTLS traffic, applications such as Microsoft Outlook stop responding while the DTLS tunnel remains active. The time of inactivity is directly related to the interval set for client DTLS DPD. By default, DPD is set to an optimal value of 30 seconds which should work in most cases.

If the client DTLS DPD is too high, failover does not occur quickly enough, and a user notices applications being unresponsive. Once the client DTLS DPD is set correctly, the customer then notices excessive loss and re-establishment of the DTLS channel. This might also be perceived as poor performance of the tunnel.

To correct this problem, do the following steps:

- 
- Step 1** Enable the client DTLS DPD and configure it to be twice the interval of the firewall idle timer.
- For example, set this value to 2 minutes when using the default setting with the third-party firewall (40 seconds). The client DTLS DPD value should be no greater than 10 minutes to ensure that TLS fallback occurs in a timely manner.
- Step 2** Enable the client DTLS keepalive and configure it to be at least 10 seconds less than the firewall idle timer default interval.
- For example, set this value to 30 seconds if using the default configuration (40 seconds) of the third-party firewall.
- If there has been an idle period of DTLS traffic, the firewall might stop sending data to the client or security appliance. The client attempts to re-establish DTLS each time this occurs up to the limit of the retry counter. The tunnel falls back to TLS during this period if the DTLS DPD is set to a sufficient value.



For example, a typical setting for DPD from both the client and security appliance might be 120 seconds. If the DTLS session is blocked by the firewall, a user experiences an outage and then eventually the session falls back to TLS. This outage is directly proportional to the value set for DTLS DPD.

DTLS is a UDP based protocol and is connectionless. There is a flow associated with the DTLS session that is based on the source and destination addresses and ports. Firewalls build a session table based on these values and track this as a unique session. By default, DTLS is enabled when SSL VPN access is enabled on an interface.

## No AnyConnect Confirmation Dialog for Cisco Secure Desktop Users

When contacting a central-site security appliance that enforces a Cisco Secure Desktop policy, the AnyConnect client no longer lets the user terminate the connection attempt prior to starting the download and execution of Cisco Secure Desktop. In AnyConnect Release 2.0, the dialog appears for each connection attempt. The AnyConnect client, Release 2.1 and higher, however, removes this dialog for Cisco Secure Desktop users, and Cisco Secure Desktop processing continues without further input from the user.

## AnyConnect Client Uses Custom-built OpenSSL Libraries Based on 0.9.8f

The AnyConnect client uses the OpenSSL cryptography libraries to perform encryption and security protocol encapsulation. A new version of OpenSSL has been released that fixes several issues in older versions of OpenSSL. The OpenSSL libraries used by the AnyConnect client have been updated by merging in 0.9.8f changes with custom Cisco changes.

AnyConnect is not exposed to the flaws found between 0.9.8f and 0.9.8j because it does not include the vulnerable code.

For more information see the following URLs:

<http://www.cve.mitre.org/cgi-bin/cvename.cgi?name=CVE-2007-4995>

<http://www.cve.mitre.org/cgi-bin/cvename.cgi?name=CVE-2007-5135>

## Optionally Disable Tearing Down Tunnel Upon Smartcard Removal

A network administrator can optionally disable tearing down a tunnel when the remote user removes the Smartcard. Some companies impose a requirement that a user must remove his/her Smartcard when the laptop is unattended. If the remote user in such a situation is downloading an application or replicating data to the central site and needs to step away from the laptop, the transfer fails and must be restarted because the tunnel has been dropped.

## Upgrading Standalone AnyConnect Client for Windows Vista Shows Activity Indication

When Windows Vista users upgrade via standalone AnyConnect client, the client briefly displays a message “Exiting. Update in progress.” and then the client exits. There is no AnyConnect or Installer windows or dialogs visible on the user's desktop for the duration of the upgrade. When the upgrade completes, the AnyConnect icon appears in the system tray.

When Windows Vista users upgrade via the browser launch of AnyConnect, the AnyConnect Downloader window is visible for the duration of the upgrade, but the Installer window is not visible. When the upgrade completes, the Downloader exits and the AnyConnect icon appears in the system tray.

## AnyConnect SBL Does Not Support Dialer and Third-Party Application Launchers

Due to the security implications, the dialer and third-party application launchers are not supported in AnyConnect Start Before Login.

## Start Before Logon and PLAP Require a Network Connection

Start Before Logon and PLAP require a network connection to be present at the time it is invoked. In some cases, this might not be possible, because a wireless connection might depend on credentials of the user to connect to the wireless infrastructure. Since SBL mode precedes the credential phase of a login, a connection would not be available in this scenario. In this case, for SBL/PLAP to work, the wireless connection must be configured to cache the credentials across login, or another wireless authentication must be configured.

## Windows Machine Cannot Be Named localhost

Microsoft allows a user to configure the machine name as “localhost” without any warnings. When a machine has the name of localhost, connections made with the SSL VPN Client or IPsec VPN Client fail.

AnyConnect Client connections fail without logs clearly outlining the issue. The AnyConnect message is “Unable to establish VPN.” IPsec VPN Client connections fail with Reason 442. To work around this issue, rename the PC to something other than localhost.

## Synchronizing a Mobile Device to a PC While a Tunnel Is Active

If you use ActiveSync or Windows Mobile Device Center to synchronize a mobile device to your PC while the tunnel is active, you must either enable Local LAN in the security appliance configuration or configure your device to use a serial port instead of Remote Network Driver Interface Specification (RNDIS).

When RNDIS is enabled, mobile devices are assigned a link-local address when they are connected to the PC. When Tunnel All is configured on the security appliance, all network traffic, including link-local traffic, is sent to the tunnel interface.

If Tunnel All is a requirement for your deployment, you can try to configure the mobile device to synchronize using a serial port interface, you can synchronize your device while Tunnel All is configured. On the Mobile Device, under Start > Settings > Connections > USB-to-PC, deselect the “Enable advanced network functionality” check box to disable RNDIS.

## Obtaining a DHCP Ethernet IP If Connected via Wireless-only First

When roaming between different network interfaces with the Cisco AnyConnect VPN Client, you might be unable to obtain an IP address via DHCP on a new interface, causing an inability to move to the new network without first tearing down the VPN session.

To work around this issue, ensure that Split Tunneling or Local LAN access is enabled. With one of these features enabled, the new local network interface can obtain a DHCP assigned IP address and the user can successfully roam.

# Caveats

Caveats describe unexpected behavior or defects in Cisco software releases. The following sections, prioritized with the latest 2.3 release first, identifies caveats with Severities 2 and 3.



## Note

If you have an account with CCO, you can use Bug Navigator II to find caveats of any severity for any release. To reach Bug Navigator II on CCO, select Software & Support: Online Technical Support: Software Bug Toolkit or navigate to [http://www.cisco.com/cgi-bin/Support/Bugtool/launch\\_bugtool.pl](http://www.cisco.com/cgi-bin/Support/Bugtool/launch_bugtool.pl).

## Open Caveats in Cisco AnyConnect VPN Client, Release 2.3.2016

Table 6 lists the caveats that are unresolved in the Cisco AnyConnect VPN client, Release 2.3.2016.

**Table 6** *Open Caveats in Cisco AnyConnect VPN Client, Release 2.3.2016*

ID	Headline
CSCsh51779	Client-side proxy & AoN tunneling: must stop direct access to proxy.
CSCsh69786	IPv6 link local addresses are not tunneled through AnyConnect Client.
CSCsi00491	Standalone can connect to wrong ASA from within SecureDesktop.
CSCsi35149	Transcend: unable to clear session from GW after setting MSIE proxy V
CSCsi44045	Difficult to clear the VPN program after tunnel cleared from GW
CSCsm92424	Random client DPD disconnects with McAfee HIPS SW.
CSCsq02996	Auto-resume sometimes fails even though head-end not timed out.
CSCsq49102	AnyConnect incompatibility with Citrix advanced gateway client 2.2.1
CSCsq88383	AnyConnect user authentication fails in some scenarios.
CSCsr23029	Standalone client fails to connect if CSD and Authenticating proxy.
CSCsu08798	AnyConnect Linux with certs fails if browser master password defined.
CSCsu52949	GUI pops up certificate warning prompts on every connection attempt.
CSCsu70199	IPv6: Network error: windows has detected and IP address conflict.
CSCsv49773	Multiple local profiles for SG may result in using wrong settings.
CSCsw28876	AnyConnect: Need to reboot PC to get localization catalog to load.
CSCsw30030	Vista: Unable to process response from using standalone AnyConnect.
CSCsw37980	AC needs more certificate matching events.
CSCsw40079	Failed to initialize VPN API aborting message while launching AC.
CSCsw85805	AnyConnect only waits 12 seconds for auth response from headend.
CSCsw97163	AC should not re-use tg cookie if group-url w/ new tg is being used.
CSCsx14777	DART:AC Standalone AnyConnect Client shows AnyConnect 2.3.xx instead of AnyConnect dart 2.3.xx.
CSCsx14838	XP:DART application not installed while connecting AC in some scenarios.
CSCsx21485	VPN agent "caches" cert information.
CSCsx25806	XP IPV6: AnyConnect can't ping assigned IPV6 address.

**Table 6** *Open Caveats in Cisco AnyConnect VPN Client, Release 2.3.2016 (continued)*

ID	Headline
CSCsx48918	RDP+SBL: Unable to retrieve logon information to verify compliance
CSCsx62325	Windows Mobile driver error with SVC rekey new-tunnel
CSCsx70548	Linux: user logoff does not disconnect VPN connection
CSCsy34111	SVC MSIE proxy option auto does not work
CSCsy48762	Split tunnel not working with Anyconnect and Windows Mobile
CSCsy73171	AnyConnect roam from EVDO car to 802.11 never reconnected
CSCsz19269	AnyConnect ignoring exclusion lists and using proxy server
CSCsz27811	Anyconnect: After cert validation error, get Connection failure unknown
CSCsz28004	AnyConnect failed authorization after certs, Connect button errors
CSCsz67246	Anyconnect SBL: XML parsing prevents concurrent connections
CSCsz78112	Long-term fix for Anyconnect with IPv6: non-English Vista
CSCsz95464	Anyconnect fails to connect with special character password "<>"
CSCsz97362	Need to document some 3rd Party inter-operability issues
CSCsz99190	AnyConnect Mac: Installer leaves vpnclient.dmg in root directory
CSCta01109	file move operation fails
CSCta11649	AnyConnect on Mac OS should be able to verify Certs from KeyChain
CSCta36014	AnyConnect API Package incorrect dependency
CSCta39434	AC - If CertificateMatch in Profile selects 0 certs, AC will use any

## Open Caveats in Cisco AnyConnect VPN Client, Release 2.3.254

[Table 7](#) lists the caveats that are unresolved in the Cisco AnyConnect VPN client, Release 2.3.254.

**Table 7** *Open Caveats in Release 2.3.254*

Id	Headline
CSCsr23029	Standalone client fails to connect if CSD and Authenticating proxy.
CSCsr77414	IOS Webvpn: SVC split-exclude shows inconsistent behavior.
CSCsu52949	GUI pops up certificate warning prompts on every connection attempt.
CSCsu94876	Linux: Not able to connect second time after upgrade.
CSCsv49773	Multiple local profiles for SG may result in using wrong settings.
CSCsv49984	Mac: user logoff does not disconnect VPN connection.
CSCsw16124	Sometimes MAC reboots after AC upgrade.
CSCsw27844	Fedora: AnyConnect could not establish DTLS connection.
CSCsw28876	AnyConnect: Need to reboot PC to get localization catalog to load.
CSCsw30030	Vista: Unable to process response from using standalone AnyConnect.
CSCsw37980	AC needs more certificate matching events.

**Table 7**      **Open Caveats in Release 2.3.254 (continued)**

<b>Id</b>	<b>Headline</b>
CSCsw40079	Failed to initialize VPN API aborting message while launching AC.
CSCsw45765	AnyConnect & CSD: Cert Validation Failed on Windows 2000.
CSCsw48370	Vista: Some times AnyConnect app minimizes before entering credentials.
CSCsw66310	AnyConnect stacks prepended domain names pushed from head end.
CSCsw85805	AnyConnect only waits 12 seconds for auth response from headend.
CSCsw97163	AC should not re-use tg cookie if group-url w/ new tg is being used.
CSCsx14777	DART:AC Standalone AnyConnect Client shows AnyConnect 2.3.xx instead of AnyConnect dart 2.3.xx.
CSCsx14838	XP:DART application not installed while connecting AC in some scenarios.
CSCsx21485	VPN agent “caches” cert information.
CSCsx25806	XP IPV6: AnyConnect can't ping assigned IPV6 address.

## Open Caveats in Cisco AnyConnect VPN Client, Release 2.3.185

Table 8 lists the caveats that are unresolved in the Cisco AnyConnect VPN Client, Release 2.3.185.

**Table 8**      **Open Caveats in Cisco AnyConnect VPN Client, Release 2.3.185**

<b>ID</b>	<b>Headline</b>
CSCsh51779	Client-side proxy & AoN tunneling: must stop direct access to proxy.
CSCsh69786	IPv6 link local addresses are not tunneled through AnyConnect Client.
CSCsi00491	Standalone can connect to wrong ASA from within SecureDesktop.
CSCsm92424	Random client DPD disconnects with McAfee HIPS SW.
CSCso79661	AnyConnect BSOD (vpnva.sys) after disconnecting session.
CSCsq02996	Auto-resume sometimes fails even though head-end not timed out.
CSCsq88383	AnyConnect user authentication fails in some scenarios.
CSCsq96716	Routing table on MAC has anyconnect route entries though user uninstalls.
CSCsr22475	AnyConnect reconnect fails when system up after hibernate.
CSCsr23029	Standalone client fails to connect if CSD and Authenticating proxy.
CSCsr52052	AnyConnect: “Package unavailable on the Peer”.
CSCsu08798	AnyConnect Linux with certs fails if browser master password defined.
CSCsu45019	Connection attempt has failed in standalone client mode on MAC.
CSCsu70199	IPv6: Network error: windows has detected and IP address conflict.
CSCsu70504	Vista IPv6: conn fails on systems where DNE was/is installed.
CSCsu94876	Linux: Not able to connect second time after upgrade.
CSCsv18171	MAC: Rekey failure and connection closed.
CSCsv49642	Linux AnyConnect: “Unable to launch Secure Desktop...” using AC standalone.
CSCsv49773	Multiple local profiles for SG may result in using wrong settings.

**Table 8** *Open Caveats in Cisco AnyConnect VPN Client, Release 2.3.185 (continued)*

ID	Headline
CSCsv76518	AnyConnect Linux fails to connect w/out root privs.
CSCsw16124	Sometimes MAC reboots after AC upgrade.
CSCsw20034	Newly downloaded profile is not properly loaded.
CSCsw37913	AC certs not found - profile template Cert Match defaults need changes.
CSCsw37980	AC needs more certificate matching events.
CSCsw40079	Failed to initialize VPN API aborting message while launching AC.
CSCsw44151	GUI crashes while sometimes getting preferences.
CSCsw45779	SBL: After login, sometimes AnyConnect UI cannot be opened on desktop.
CSCsw45828	Setting for autoreconnect behavior is not saved.

## Resolved Caveats

The following sections identify the caveats that each Release 2.3 build resolves.

### Caveats Resolved in AnyConnect Release 2.3.2016

Table 9 shows the caveats that AnyConnect VPN Client, Release 2.3.2016 resolves.

**Table 9** *Resolved Caveats by Cisco AnyConnect VPN Client, Release 2.3.2016*

ID	Headline
CSCsl20808	[ENH] Allow AnyConnect to connect to user-specified SSL port
CSCsq48784	AnyConnect does not restore flushed firewall rules
CSCsq96716	Routing table on MAC has anyconnect route entries though user uninstalls.
CSCsr52052	AnyConnect: "Package unavailable on the Peer".
CSCsu45019	Connection attempt has failed in standalone client mode on MAC.
CSCsu70504	Vista IPv6: conn fails on systems where DNE was/is installed.
CSCsv49984	Mac: user logoff does not disconnect VPN connection.
CSCsv76518	AnyConnect Linux fails to connect w/out root privs.
CSCsw45765	AnyConnect & CSD: Cert Validation Failed on Windows 2000.
CSCsw66310	AnyConnect stacks prepended domain names pushed from head end.
CSCsx25329	SBL not working on Vista Client machine
CSCsx35067	Launching AnyConnect using Start Menu shortcut may not show window
CSCsx56412	AC on XP & Linux over L2TP (no IPsec) does not pass traffic, disconnects
CSCsx79055	Upgrade during SBL incomplete
CSCsx96885	AnyConnect does not connect if the split tunnel ACL has duplicates
CSCsy05414	Anyconnect translation template missing 'Certificate Validation Failure'
CSCsy13010	Linux client does not display appropriate msg if pkg is missing on ASA

**Table 9** *Resolved Caveats by Cisco AnyConnect VPN Client, Release 2.3.2016 (continued)*

ID	Headline
CSCsy13661	AnyConnect standalone does not log out of ASA on connection error
CSCsy43236	AnyConnect does not allow NetBIOS broadcast requests
CSCsy44786	GUI fails when users log off using SBL
CSCsy47162	Certificate match can fail in some situations
CSCsy59024	Error decompressing large ICMP fragments
CSCsy72485	Takes approx 2 mins for the homepage to load with AnyConnect
CSCsz43626	Anyconnect with IPv6: connection fails on non-English Vista
CSCsz75000	Anyconnect with CSD on Vista using machine certificates fails to connect
CSCta21437	AnyConnect: Safesign CSP prompts for PIN using AAA
CSCsx56412	AC on XP & Linux over L2TP (no IPsec) does not pass traffic, disconnects
CSCta23593	Agent needs to turn off sigchild handler when forking to verify certs

## Caveats Resolved in AnyConnect Release 2.3.254

Table 10 shows the caveats that AnyConnect VPN Client, Release 2.3.254 resolves.

**Table 10** *Caveats Resolved by Cisco AnyConnect VPN Client, Release 2.3.254*

ID	Headline
CSCso79661	AnyConnect BSOD (vpnva.sys) after disconnecting session.
CSCsu22088	Allow AnyConnect session from a single RDP session.
CSCsv18171	Mac AnyConnect client reports rekey failure on reconnect.
CSCsv83524	AnyConnect triggers Anti Spyware module of NetBarrier X5 on Mac 10.5.
CSCsw20034	Newly downloaded profile is not properly loaded.
CSCsw27490	Username field is empty in connect to field using weblaunch with proxy.
CSCsw31388	Client creates multiple SSL sessions in WinXP.
CSCsw37913	AC certs not found - profile template CertsMatch defaults need changes.
CSCsw44151	GUI crashes sometimes getting preferences.
CSCsw45589	SBL: AnyConnect status bar does not show host it connected
CSCsw45779	SBL: After login, sometimes AnyConnect UI cannot be opened on desktop.
CSCsw45828	Setting for autoreconnect behavior is not saved.
CSCsw51554	AC: endpoint.feature='failure'&endpoint.os.version='Pocket%20PC'.
CSCsw52317	AnyConnect: Handling presentation of error codes differently.
CSCsw69460	AnyConnect fails to uninstall with svc keep installer none.
CSCsw72917	AnyConnect Mac client may crash when pressing the Select button.
CSCsw75828	No posture assessment messages on MAC AnyConnect client.
CSCsw87978	Fix for CSCsv14957 broke NSS lib.
CSCsw90948	AC client text Please enter username and password for cert-only connection.

**Table 10** *Caveats Resolved by Cisco AnyConnect VPN Client, Release 2.3.254 (continued)*

ID	Headline
CSCsw91397	AnyConnect may log error regarding “Invalid sdi token”.
CSCsx03514	Windows install fails when transform applied.
CSCsx13160	MAC: AnyConnect help page window is blank.

## Caveats Resolved by AnyConnect Release 2.3.185

Table 11 shows the caveats that AnyConnect VPN Client, Release 2.3.185 resolves.

**Table 11** *Caveats Resolved by Cisco AnyConnect VPN Client, Release 2.3.185*

Id	Headline
CSCsh81003	XP: After failed conn, client reports “Internal Error” and needs restart.
CSCsi53608	AnyConnectCSCOTUN0 interface does not install under SuSE Linux.
CSCsi69205	smart card cant be used with MAC anyconnect client.
CSCsk05393	avoid Multiple Auth requests for every AnyConnect--TPM.
CSCsk25563	MAC OS X AnyConnect client fails to connect to Load Balancing IP.
CSCsk74884	Clicking entry in profile drop-down fails on subsequent connections.
CSCsl01485	Client does nothing when <enter> pressed in password input field.
CSCsl71917	AnyConnect fails to launch CSD with certificate authentication.
CSCsm48367	The VPN downloader can be mistakenly downloaded on every connection.
CSCsm60339	Sleep/Resume Cycles on Vista non-responsive tcpipreg.sys - VA failure.
CSCsm98903	AnyConnect 2.x fails via HTTP Proxy if no DNS lookup configured on user PC.
CSCso17621	Suspend/resume not handled on Mac.
CSCso17627	need ability to disable reconnects on PC resume or connection loss.
CSCso28633	Duplicate AnyConnect icon in tray after client upgrade.
CSCso31229	Anyconnect standalone fails to connect to Group url on first attempt.
CSCso57937	Entering Group-URL in “Connect to” doesn't work.
CSCso60940	Agent does not fully restore browser proxy settings on user logoff.
CSCso65751	Release Notes for Cisco AnyConnect VPN Client, Release 2.2 wrong BUG ID.
CSCso67063	AnyConnect: Suppress the showing of the message box on reconnect.
CSCso73079	AnyConnect package install fail with Unicode chars Windows username.
CSCso73889	Challenge response string gets cut off without resizing window.
CSCso78492	Incorrect ownership of installed files in Cisco AnyConnect VPN Client.ap.
CSCso89871	AnyConnect: The VPN client agent SSL engine encountered an error.
CSCso92848	Vista - Slow connection re-establishment.
CSCsq03009	After Disconnect, Select button must be clicked 2x to reconnect.
CSCsq34500	Linux client fails to upgrade after web-based install.
CSCsq34522	Mac client fails to upgrade after web-based install.



**Table 11** *Caveats Resolved by Cisco AnyConnect VPN Client, Release 2.3.185 (continued)*

CSCsq50583	vpnagent crash on XP after returning from hibernate (tunnel up).
CSCsq63883	AnyConnect: Implement preflight checks for installer.
CSCsq64710	With EVDO card, DNS queries are sent to the wrong DNS servers.
CSCsq73897	Mac client split-exclude only works with direct attached networks.
CSCsr07346	Anyconnect uses SSLv3 instead of TLSv1 with Linux / MAC client.
CSCsr08612	Rekey failure message on Windows AnyConnect client machine.
CSCsr19243	Connection via AnyConnect GUI on OS X doesn't validate some certificates.
CSCsr19310	AnyConnect GUI for OS X creates symlinks; requires admin privileges.
CSCsr42499	WTS messages from the agent only show half the text.
CSCsr46257	Password lifetime/exposure changes in UI components.
CSCsr59516	AC Mac Intel crashes when launching CSD.
CSCsr65273	Anyconnect - R6025 -pure virtual function call error when quit.
CSCsr84612	Win2k3 Server tunnel-all allows local LAN traffic.
CSCsu42358	Not able to ping the Anyconnect IP on MAC when use Split include.
CSCsu54601	AnyConnect error "Administrator privileges are required" needs more info.
CSCsu75044	Posture Assessment Failure with Secure Desktop ON.
CSCsu79086	AnyConnect fails to connect if port value is specified.
CSCsu80972	vpnu.exe crash on launch.
CSCsu82174	Preference SBL should be global for all users.
CSCsu83713	Could not see the user preferences when group url is entered in connect.
CSCsu88022	vpndownloader.exe - Application error with core dump.
CSCsu88306	AnyConnect SBL GUI moves around the desktop before centering.
CSCsu89638	Export stats fails on Japanese Windows XP.
CSCsu89916	Launch AC client on MAC failing with client driver error.
CSCsu91359	Upgrade / Weblaunch issues due to Windows User Profile configuration.
CSCsu92080	MAC: Web Install unsuccessful.
CSCsu94180	Disconnect on Suspend preference is not working.
CSCsu94752	MAC: Split exclude traffic going through the tunnel
CSCsu99068	Some Preferences not showing in SBL mode after client machine is UP.
CSCsu99903	MAC: Crash when access preferences with preFill user name.
CSCsv12615	AC template file and xsd file not created on Linux.
CSCsv14957	Standalone client on RedHatv4 is not connecting!
CSCsv17829	Auto reconnect behavior is not available for Windows/MAC.
CSCsv18464	MAC: Reconnect after IP address change cannot connect.
CSCsv37062	doc anyconnect admin guide dtls port number example wrong.
CSCsv51989	MAC: Traffic not passing through after Auto reconnect.
CSCsv52806	Agent does not load at startup on MAC.

**Table 11** *Caveats Resolved by Cisco AnyConnect VPN Client, Release 2.3.185 (continued)*

CSCsv60029	Copyright text displayed in Mac UI scrolled incorrectly.
CSCsv62553	Upgrade: LAN Access preference not set true on linux/MAC.
CSCsv63993	Upgrade: default user name group not shown on Standalone AnyConnect client.
CSCsv76603	Get Certificate button looks odd on Windows XP only.
CSCsv88763	MAc 10.4: User messages are truncated some times.
CSCsv92358	GUI does not display IPv6 address on main tab, only stats tab.

## Notices/Licensing

See the following sections for Cisco AnyConnect VPN Client license information.

### License Options

For brief descriptions and example product numbers (SKUs) of the AnyConnect user license options, see [Cisco Secure Remote Access: VPN Licensing Overview](#).

For the latest detailed information about the AnyConnect user license options, see [Managing Feature Licenses](#) in the *Cisco ASA 5500 Series Configuration Guide using the CLI*, 8.2.

### End-User License Agreement

For information on the end-user license agreement, see:  
[http://www.cisco.com/univercd/cc/td/doc/es\\_inpk/euljen\\_\\_.pdf](http://www.cisco.com/univercd/cc/td/doc/es_inpk/euljen__.pdf)

### OpenSSL/Open SSL Project

This product includes software developed by the OpenSSL Project for use in the OpenSSL Toolkit (<http://www.openssl.org/>).

This product includes cryptographic software written by Eric Young (eay@cryptsoft.com).

This product includes software written by Tim Hudson (tjh@cryptsoft.com).

For Open Source License information for this product, please see the following link:  
<http://www.cisco.com/en/US/docs/security/asa/asa80/license/opensrce.html#wp50053>.

## Related Documentation

For more information, refer to the following documentation:

- For additional information about the security appliance or ASDM or its platforms, see *Navigating the Cisco ASA 5500 Series Documentation*:  
<http://www.cisco.com/en/US/docs/security/asa/roadmap/asaroadmap.html>
- Cisco AnyConnect VPN Client, Release 2.2, Administrator Guide*

- *Cisco Secure Desktop Configuration Guide for Cisco ASA 5500 Series Administrators*

CCDE, CCENT, CCSI, Cisco Eos, Cisco HealthPresence, Cisco IronPort, the Cisco logo, Cisco Lumin, Cisco Nexus, Cisco Nurse Connect, Cisco Pulse, Cisco StackPower, Cisco StadiumVision, Cisco TelePresence, Cisco Unified Computing System, Cisco WebEx, DCE, Flip Channels, Flip for Good, Flip Mino, Flipshare (Design), Flip Ultra, Flip Video, Flip Video (Design), Instant Broadband, and Welcome to the Human Network are trademarks; Changing the Way We Work, Live, Play, and Learn, Cisco Capital, Cisco Capital (Design), Cisco:Financed (Stylized), Cisco Store, and Flip Gift Card are service marks; and Access Registrar, Aironet, AllTouch, AsyncOS, Bringing the Meeting To You, Catalyst, CCDA, CCDP, CCIE, CCIP, CCNA, CCNP, CCSP, CCVP, Cisco, the Cisco Certified Internetwork Expert logo, Cisco IOS, Cisco Press, Cisco Systems, Cisco Systems Capital, the Cisco Systems logo, Cisco Unity, Collaboration Without Limitation, Continuum, EtherFast, EtherSwitch, Event Center, Explorer, Fast Step, Follow Me Browsing, FormShare, GainMaker, GigaDrive, HomeLink, iLYNX, Internet Quotient, IOS, iPhone, iQuick Study, IronPort, the IronPort logo, Laser Link, LightStream, Linksys, MediaTone, MeetingPlace, MeetingPlace Chime Sound, MGX, Networkers, Networking Academy, Network Registrar, PCNow, PIX, PowerKEY, PowerPanels, PowerTV, PowerTV (Design), PowerVu, Prisma, ProConnect, ROSA, ScriptShare, SenderBase, SMARTnet, Spectrum Expert, StackWise, The Fastest Way to Increase Your Internet Quotient, TransPath, WebEx, and the WebEx logo are registered trademarks of Cisco Systems, Inc. and/or its affiliates in the United States and certain other countries.

All other trademarks mentioned in this document or website are the property of their respective owners. The use of the word partner does not imply a partnership relationship between Cisco and any other company. (0908R)

Any Internet Protocol (IP) addresses and phone numbers used in this document are not intended to be actual addresses and phone numbers. Any examples, command display output, network topology diagrams, and other figures included in the document are shown for illustrative purposes only. Any use of actual IP addresses or phone numbers in illustrative content is unintentional and coincidental.

© 2009 Cisco Systems, Inc. All rights reserved.

